

SEVV step



SEVV step







Alison Smith



Previously published as *The Sewing Book*



LONDON, NEW YORK, MUNICH, MELBOURNE. DELHI

DK INDIA

Editor Alicia Ingty

Assistant Editor Ekta Sharma

Senior Art Editor Neha Ahuja

Assistant Art Editors Divya PR, Era Chawla, Mansi Nagdev, Mini Dhawan

Editorial Manager Glenda Fernandes

Senior Art Editor (Lead) Navidita Thapa

Production Manager Pankaj Sharma

DTP Manager Sunil Sharma

Senior DTP Designers Dheeraj Arora, Jagtar Singh

DTP Designer Tarun Sharma

Assistant DTP Designer Sourabh Challariya

DK UK

Project Editor Danielle Di Michiel
Project Art Editor Jane Ewart
US Editors Rebecca Warren, Jenny Siklos
Editorial Assistant Roxanne Benson-Mackey
Managing Editor Dawn Henderson
Managing Art Editor Marianne Markham
Senior Jacket Creative Nicola Powling
Production Editor Ben Marcus
Senior Production Controller Alice Sykes
Creative Technical Support Sonia Charbonnier

First American Edition, 2011
Published in the United States by DK Publishing
375 Hudson Street New York, New York 10014

11 12 13 10 9 8 7 6 5 4 3 2 1 001-179845-Feb/2011 Copyright © 2011 Dorling Kindersley Limited All rights reserved

Without limiting the rights under copyright reserved above, no part of this publication may be reproduced, stored in a retrieval system, or transmitted, in any form, or by any means (electronic, mechanical, photocopying, recording, or otherwise), without the prior written permission of both the copyright owner and the above publisher of this book.

Published in Great Britain by Dorling Kindersley Limited.

A catalog record for this book is available from the Library of Congress.


ISBN 978-0-7566-7164-8

DK books are available at special discounts when purchased in bulk for sales promotions, premiums, fund-raising, or educational use. For details, contact: DK Publishing Special Markets, 375 Hudson Street, New York, New York 10014 or SpecialSales@dk.com.

Color reproduction by Media Development & Printing Ltd Printed and bound in Singapore by Tien Wah Press

Discover more at www.dk.com


Previously published as The Sewing Book





CONTENTS

Introduction		6	Pockets	140
Sewing eq	uipment	8	Waistline, belts, and tie-backs	150
Fabrics		28	Facings and necklines	168
Stitch esse	entials	46	Collars	180
Patterns		64	Sleeves and sleeve finishes	188
Gathers, ruffles, tucks, darts,			Decorative techniques	208
and plea	ts	80	Glossary	214
Hems and	edges	104	Index	219
Fasteners		118	Acknowledgments	224




INTRODUCTION

If you are new to sewing and eager to master the key techniques, Sew Step by Step is the book for you. These clearly laid out pages cover all the basics (plus a bit more) to help you make and restyle simple home goods, clothes, and accessories.

Starting with equipment and notions and moving on through fabrics to the many techniques, *Sew Step by Step* demonstrates all the basic stitches, shows you how to master seams, hems, and edges, teaches you easy ways to add shape to clothing, with gathers, darts, and waistlines, and how to finish your work with pockets and fasteners.

I hope this book will encourage you to enjoy this satisfying hobby, and inspire you to create beautiful things—for yourself or for your family and friends.

Happy Sewing!









SEWING EQUIPMENT

Basic sewing kit

A well-equipped sewing kit will include all of the items shown below and many more, depending on the type of sewing that you do regularly. It is important that a suitable container is used to keep your tools together, so that they will

be readily at hand, and to keep them organized.

Thimble

This is useful to protect the end of your finger when hand sewing. Thimbles are available in various shapes and sizes. See page 16.

Tape measure

Essential, not only to take body measurements, but also to help measure fabric, seams, etc. Choose one that gives both inches and centimeters. A tape made of plastic is best as it will not stretch. See page 14.

Zippers.

It is always a good idea to keep a couple of zippers in your sewing kit. Black, cream, and navy are the most useful colors. See pages 133–139.

Threads

A selection of threads for hand sewing and machine/ serger sewing in a variety of colors. Some threads are made of polyester, while others are cotton or rayon. See pages 20–21.

Notions

All the odds and ends a sewer needs, including everything from buttons and snaps to trims and elastic. A selection of buttons and snaps in your basic kit is useful for a quick repair. See pages 18–19.

Pins

Needed by every sewer to hold the fabric together prior to sewing it permanently. There are different types of pins for different types of work. See page 23.

Safety pins

In a variety of sizes and useful for emergency repairs as well as threading elastics. See page 23.



Embroidery scissors Small pair of scissors with very sharp points, to clip threads close to the fabric. See page 13.

Cutting shears

Required for cutting fabric. When buying, select a pair that feels comfortable in your hand and that is not too heavy. See pages 12–13.

Needles

A good selection of different types of needles for sewing by hand. This will enable you to tackle any hand sewing project . See page 22.

Seam ripper

To remove any stitches that have been sewn in the wrong place. Various sizes of seam rippers are available. Keep the cover on when not in use to protect the sharp point. See page 12.

Pin cushion

To keep your needles and pins safe and clean. Choose one that has a fabric cover and is firm. See page 23.

Sewing gauge

A handy gadget for small measurements. The slide can be set to measure hem depths, buttonhole diameters, and much more. See page 14.

Buttonhole cutter

An exceedingly sharp knife that gives a clean cut through machine buttonholes. Place a cutting mat underneath when using this tool, or you might damage the blade. See page 12.

BUILD UP YOUR SEWING KIT

CUTTING TOOLS 12-13

Bent-handled shears Paper scissors Pinking shears Snips Trimming scissors

MEASURING TOOLS 14

Other tape measures

MARKING AIDS 15

Chalk pencil Chalk cartridge pencil Tailor's chalk Tracing wheel and carbon paper Water/air-soluble pen

USEFUL EXTRAS 16

14-In-1 measure
Beeswax
Collar point turner
Emergency sewing kit
Glue stick
Liquid sealant
Loop turner
Tweezers

NEEDLE THREADERS 22

PRESSING AIDS 17

Iron Ironing board Pressing cloth Pressing mitten Tailor's ham

Cutting tools

There are many types of cutting tools, but one rule applies to all: buy good-quality products that can be re-sharpened. When choosing cutting shears, make sure that they fit the span of your hand—this means that you can comfortably open the whole of the blade with one action, which is very important to allow clean and accurate cutting lines. Shears and scissors of various types are not the only cutting tools that are required, as everyone will at some time need a seam ripper to remove misplaced stitches or to unpick seams for mending.





Measuring tools and marking aids

A huge range of tools enables a sewer to measure accurately. Choosing the correct tool for the task at hand is important, so that your measurements are precise. The next step is to mark your work using the appropriate marking technique or tool.

Measuring tools

There are many tools available to help you measure everything from the width of a seam or hem, to body dimensions, to the area of a window. One of the most basic yet invaluable measuring tools is the tape measure. Be sure to keep yours in good condition—once it stretches or gets snipped on the edges, it will no longer be accurate and should be replaced.



← Metal tape for windows

A metal tape that can be secured when extended is used to measure windows and soft furnishings.



Available in various colors and widths. Try to choose one that is the same width as standard seam allowance (%in / 1.5cm), because it will prove very useful.



Retractable tape →

Very useful to have in your purse when shopping as you never know when you may need to measure something!



← Extra-long tape

This is usually twice the length of a normal tape measure, at 10ft (300cm) long. Use it when making home goods. It's also useful to help measure the length of bridal trains.




← Sewing gauge

A handy small tool about 6in (15cm) long, marked in inches and centimeters, with a sliding tab. Use as an accurate measure for small measurements such as hems.



Marking aids

Marking certain parts of your work is essential, to make sure that things like pockets and darts are placed correctly and seamlines are straight as drawn on the pattern. With some marking tools, such as pens and a tracing wheel and carbon paper, it is always a good idea to test on a scrap of fabric first to make sure that the mark made will not be permanent.



← Chalk pencil

Available in blue, pink, and white. As it can be sharpened like a normal pencil, it will draw accurate lines on fabric.



These two items are used together to transfer markings from a paper pattern or a design on to fabric. Not suitable for all types of fabric though, as marks may not be able to be removed easily.

← Water/air-soluble pen

This resembles a felt marker. Marks made can be removed from the fabric with either a spray of water or by leaving to air-dry. Be careful—if you press over the marks, they may become permanent.

← Tailor's chalk

Also known as French chalk, this solid piece of chalk in either a square or triangular shape is available in a large variety of colors. The chalk easily brushes off fabric.

← Chalk cartridge pencil

Chalk leads of different colors can be inserted into this pencil, making it a very versatile marking tool. The leads can be sharpened.




Useful extras

There are many more accessories that can be purchased to help with your sewing, and knowing which products to choose and for which job can be daunting. The tools shown here can be useful aids, although it depends on the type of sewing that you do—dressmaking, craft work, making soft furnishings, or running repairs—as to whether you would need all of them in your sewing kit.



← Beeswax

When hand sewing, this will prevent the thread from tangling, and will strengthen it. First draw the thread through the wax, then press the wax into the thread by running your fingers along it.




This is excellent for pushing out those hard-to-reach corners in collars and cuffs.



14-in-1 measure →

A strange-looking tool that has 14 different measurements on it.
Use to turn hems or edges accurately. Available in both inches and centimeters.



Bias tape maker 1

Available in ½, ¾, and 1 in (12, 18, and 25mm) widths, this tool evenly folds the edges of a fabric strip, which can then be pressed to make binding.



An essential item for many sewers, to protect the middle finger from the end of the needle. Choose a thimble that fits your finger comfortably as there are many varieties to choose from



These can be used for removing stubborn basting stitches that have become caught in the machine stitching. An essential aid to threading the serger.


Liquid sealant →

Used to seal the cut edge of ribbons and trims to prevent fraying. Also useful to seal the ends of serger stitching.



Similar to a glue stick for paper, this will hold fabric or trims temporarily in place until they can be secured with stitches. It will not damage the fabric or make the sewing needle sticky.





All the absolute essentials to fix loose buttons or dropped hems while away from your sewing machine. Take it with you when traveling.



A thin metal rod with a latch at the end. Use to turn narrow fabric tubes or to thread ribbons through a slotted lace.





Pressing aids

Successful sewing relies on successful pressing. Without the correct pressing equipment, sewing can look too "homemade," whereas if correctly pressed, any sewn item will have a neat, professional finish.





darts and the shape into curves of collars and shoulders,

and in making tailored garments.

Notions

The term notions covers all the bits and pieces that sewers tend to need, for example fasteners such as buttons, snaps, hooks and eyes, and VelcroTM. But notions also includes elastics, ribbons, trims of all types, and boning.

Buttons

Buttons can be made from almost anything—shell, bone, coconut, nylon, plastic, brass, silver. They can be any shape, from geometric to abstract to animal shapes. A button may have a shank or have holes on the surface to enable it to be attached to fabric.



Other fasteners

Hooks and eyes (below left), snaps (below center), and VelcroTM (below right) all come in a wide variety of forms, differing in size, shape, and color. Some hooks and eyes are designed to be seen, while snaps and VelcroTM are intended to be hidden fasteners.










Trims, decorations, fringes, and braids

Decorative finishing touches—fringes, strips of sequins, braids, feathers, pearls, bows, flowers, and beads—can dress up a garment, embellish a bag, or personalize soft furnishings. Some are designed to be inserted into seams, while others are surface-mounted.



Ribbons

From the narrowest strips to wide widths, ribbons are made from a variety of yarns, such as nylon, polyester, and cotton. They can be printed or plain and may feature metallic threads or wired edges.



Elastic

Elastic is available in many forms, from very narrow, round cord to wide strips (below left). It may have buttonhole slots in it (below right) or even have a decorative edge.



Boning

You can buy various types of boning in varying widths. Polyester boning (bottom left), used in boned bodices, can be sewn through, while nylon boning (bottom right), also used on boned bodices, has to be inserted into a casing. Specialist metal boning (below left and right), which may be either straight or spiral, is for corsets and bridal wear.





Threads

There are so many threads available and knowing which ones to choose can be confusing. There are specialist threads designed for special tasks, such as machine embroidery or quilting. Threads also vary in fiber content, from pure cotton to rayon to polyester. Some threads are very fine, while others are thick and coarse. Failure to choose the correct thread can spoil your project and lead to problems with the stitch quality of the sewing machine.

Cotton thread ↓

A 100% cotton thread. Smooth and firm, this is designed to be used with cotton fabrics and is much favored by quilters.



Elastic thread ↓

A thin, round elastic thread normally used on the bobbin of the sewing machine for stretch effects such as shirring.



Metallic thread ↓

A rayon and metal thread for decorative machining and machine embroidery. This thread usually requires a specialist sewing-machine needle.



Embroidery thread ↓

Often made from a rayon yarn for shine. This is a finer thread designed for machine embroidery. Available on much larger reels for economy.









Polyester all-purpose thread \downarrow

A cotton-coated polyester thread that has a very slight "give," making it suitable to sew all types of fabrics and garments, as well as home goods. The most popular type of thread.



Button thread ↓

A thicker polyester thread used for decorative top-stitching and buttonholes. Also for hand sewing buttons on thicker fabrics and some soft furnishings.



Needles and pins

Using the correct pin or needle for your work is so important, as the wrong choice can damage fabric or leave small holes. Needles are made from steel and pins from steel or occasionally brass. Take care of them by keeping pins in a pin cushion and needles in a needle case—if kept together in a small container, they could become scratched and blunt.

Needles and threaders

Needles are available for all types of fabrics and projects. A good selection of needles should be at hand at all times, whether it be for emergency mending of tears, or sewing on buttons, or adding trims to special-occasion wear. With a special needle threader, inserting the thread through the eye of the needle is simplicity itself.

← Sharps

A general-purpose hand-sewing needle, with a small, round eye. Available in sizes 1 to 12. For most hand sewing use a size 6 to 9.

$\mathsf{Darning} \to$

A long, thick needle that is designed to be used with wool or thick yarns and to sew through multiple layers.

← Quilting or betweens

Similar to a milliner's needle but very short, with a small, round eye. Perfect for fine hand stitches and favored by quilters.

Chenille →

This looks like a tapestry needle, but it has a sharp point. Use with thick or wool yarns for darning or heavy embroidery.

← Beading

Long and extremely fine, to sew beads and sequins to fabric. As it is prone to bending, keep it wrapped in tissue when not in use.

Self-threading needle →

A needle that has a double eye.

The thread is placed in the upper eye through the gap, then pulled into the eye below for sewing.

← Tapestry

A medium-length, thick needle with a blunt end and a long eye. For use with wool yarn in tapestry. Also for darning in serger threads.

Milliner's or straw →

A very long, thin needle with a small, round eye. Good for hand sewing and basting as it doesn't damage fabric. A size 8 or 9 is most popular.

← Bodkin

A strange-looking needle with a blunt end and a large, fat eye. Use to thread elastic or cord. There are larger eyes for thicker yarns.

Crewel →

Also known as an embroidery needle, a long needle with a long, oval eye that is designed to take multiple strands of embroidery thread.

← Wire needle threader

A handy gadget, especially useful for needles with small eyes. Also helpful in threading sewing-machine needles.

← Automatic needle threader

This threader is operated with a small lever. The needle, eye down, is inserted and the thread is wrapped around.



Pins

There is a wide variety of pins available, in differing lengths and thicknesses, and ranging from plain household pins to those with colored balls or flower shapes on their ends.



Straight 1

General-purpose pins of a medium length and thickness. Can be used



Dressmaker's 1

Similar to a straight pin in shape and thickness, but slightly longer. These are the pins for beginners to choose.



Pearl-headed 1

Longer than straight pins, with a colored pearl head. They are easy to pick up and use.



Glass-headed ↑

Similar to pearl-headed pins but shorter. They have the advantage that they can be pressed over without melting.



Safety pins →


Available in a huge variety of sizes and made either of brass or stainless steel. Used for holding two or more layers together.





Extra fine ↑

Extra long and extra fine, this pin is favored by many professional dressmakers because it is easy to use and doesn't damage finer fabrics.



Pin cushions 1

To keep pins clean and sharp. Choose a fabric-cover: a foam cushion may blunt pins.

Sewing machine

A sewing machine will quickly speed up any job, whether it be a quick repair or a huge home-sewing project. Most sewing machines today are aided by computer technology, which enhances stitch quality and ease of use. Always spend time trying out a sewing machine before you buy, to really get a feel for it.

Threading guides

Markings to help guide you in threading the machine.

Tension dial

To control the stitch tension on the upper thread, i.e. how fast the thread feeds through the sewing machine.

Automatic needle threader

Buttonhole sensor

A pull-down sensor that automatically judges the size of the buttonhole required to fit the button chosen......

Needle

The machine needle. Replace regularly to ensure good stitch quality. See page 26.

Presser foot

To hold the fabric in place while sewing. Various feet can be used here to aid different sewing processes. See pages 26–27.

Removable free arm

This section of the machine will pull away to give a narrow work bed that can be used when inserting sleeves. It also contains a useful storage section...

JANOME



To hold the various feet in place.

These metal teeth grip.....

Dog feeds

the fabric and feed it

through the machine.

A transparent removable cover reveals the bobbin. This plate is gridded to help stitch seams of various widths.

: Needle plate

24

Sewing equipment

Speed control

. Buttons

To provide various functions, such as reverse, locking stitch, and needle-in.

A slide, to control the speed of your machine.

Spool holder

To hold your sewing thread in place.

. Bobbin winder

Winds the thread from the spool on to the bobbin, keeping it under tension. See page 26.

. Balance wheel

This can be turned toward you to move the needle up or down manually.

.LCD screen

An illuminated screen that indicates which stitch you are using.

Touch buttons

Use these to change the type of stitch you are using and to increase and decrease the size and width of stitch.

: Touch buttons

These quickly select the most popular

stitches such as zigzag and buttonhole.

:Stitch library

All the different stitches this machine can stitch. You just have to key in the number.

Sewing-machine accessories

Many accessories can be purchased for your sewing machine to make certain sewing processes so much easier. There are different machine needles not only for different fabrics, but also for different types of threads. There is also a huge number of sewing-machine feet, and new feet are constantly coming on to the market. Those shown here are some of the most popular.

PLASTIC BOBBIN



The bobbin is for the lower thread. Some machines take plastic bobbins, others metal. Always check which kind of bobbin your machine uses as the incorrect choice can cause stitch problems.

METAL BOBBIN



Also known as a universal bobbin, this is used on many types of sewing machines. Be sure to check that your machine needs a metal bobbin before you buy.

MACHINE NEEDLES

There are different types of sewing machine needles to cope with different fabrics. Machine needles are sized from 60 to 100, a 60 being a very fine needle. There are special needles for machine embroidery and also for metallic threads.

EMBROIDERY FOOT



A clear plastic foot with a groove underneath that allows linear machine embroidery stitches to pass under.

BUTTONHOLE FOOT



This extends and the button is placed in the back of the foot. The machine will sew a buttonhole to fit due to the buttonhole sensor.

26

ROLLED HEM FOOT



This foot rolls the fabric while sewing with a straight stitch or a zigzag stitch.

BLIND HEM FOOT



Use this foot in conjunction with the blind hem stitch to create a neat hemming stitch.

ZIPPER FOOT



This foot fits to either the right or left-hand side of the needle to enable you to sew close to a zipper.

OVEREDGE FOOT



A foot that runs along the raw edge of the fabric and holds it stable while an overedge stitch is worked.

WALKING FOOT



This odd-looking foot "walks" across the fabric, so that the upper layer of fabric does not push forward. Great for matching checkers and stripes and also for difficult fabrics, like quilts.

INVISIBLE ZIPPER FOOT



A foot that is used to insert a concealed zipper—the foot holds open the coils of the zipper, enabling you to sew behind them.



FABRICS

Wool fabrics

A natural fiber, wool comes primarily from sheep—Australian merino sheep's wool is considered to be the best. However, we also get wool fibers from goats (mohair and cashmere), rabbits (angora), camels (camel hair), and llamas (alpaca). A wool fiber is either short and fluffy, when it is known as a woollen yarn, or it is long, strong, and smooth, when it is called worsted. The term virgin (or new) wool denotes wool fibers that are being used for the first time. Wool may be reprocessed or reused and is then often mixed with other fibers.

PROPERTIES OF WOOL

- comfortable to wear in all climates as it is available in many weights and weaves
- warm in the winter and cool in the summer, because it will breathe with your body
- absorbs moisture better than other natural fibers—will absorb up to 30 percent of its weight before it feels wet
- · flame-resistant

- relatively crease-resistant
- ideal to tailor as it can be easily shaped with steam
- · often blended with other fibers to reduce the cost of fabric
- felts if exposed to excessive heat, moisture, and pressure
- will be bleached by sunlight with prolonged exposure
- · can be damaged by moths

CASHMERE

Wool from the Kashmir goat, and the most luxurious of all the wools. A soft yet hard-wearing fabric available in different weights. **Cutting out:** as cashmere often has a slight pile, use a nap layout

Seams: plain, neatened with serger stitch or pinking shears (a zigzag stitch would curl the edge of the seam) Thread: a silk thread is ideal, or a polyester all-purpose thread Needle: machine size 12/14, depending on the thickness of the fabric; sharps for hand sewing Pressing: steam iron on a steam setting, with a pressing cloth and

Use for: jackets, coats, men's wear; knitted cashmere yarn for sweaters, cardigans

CHALLIS

A fine wool fabric, made from a worsted yarn that has an uneven surface texture. Challis is often printed as well as plain.

Cutting out: a nap layout is not required unless the fabric is printed

Seams: plain, neatened with serger or zigzag stitch; a run and fell seam can also be used

Thread: polyester all-purpose thread

seam roll

Needle: machine size 11/12; sharps for hand sewing

Pressing: steam iron on a steam setting, with a pressing cloth; fabric will stretch while warm so handle with care

Use for: dresses, jackets, garments with pleating or draping detail



CREPE

A soft fabric made from a twisted yarn, which is what produces the uneven surface. It is important to preshrink this fabric prior to use by giving it a good steaming, because it will have stretched on the bolt and it is prone to shrinkage.

Cutting out: use a regular layout **Seams:** plain, neatened with

serger (a zigzag stitch may curl the edge of the seam)

Thread: polyester all-purpose thread

Needle: machine size 12; sharps or milliner's for hand sewing **Pressing:** steam iron on a wool setting; a pressing cloth is not

always required

Use for: all types of clothing



FLANNEL

A wool with a lightly brushed surface, featuring either a plain or twill weave. Used in the past for underwear.

Cutting out: use a nap layout Seams: plain, neatened with serger or zigzag stitch or Hong Kong finish

Thread: polyester all-purpose thread Needle: machine size 14:

sharps for hand sewing

Pressing: steam iron on a wool setting with a pressing cloth; use a seam roll as the fabric is prone to marking

Use for: men's wear, bedding, sleepwear



A hard-wearing suiting fabric with a distinctive weave. Gabardine often has a sheen and is prone to shine. It can be difficult to handle as it is springy and frays badly. Cutting out: a nap layout is advisable as the fabric has

Seams: plain, neatened with serger or zigzag stitch

Thread: polvester all-purpose thread or 100% cotton thread Needle: machine size 14;

sharps for hand sewing

Pressing: steam iron on a wool setting; use just the toe of the iron and a silk organza pressing cloth as the fabric will mark and may shine

Use for: men's wear, iackets, pants





MOHAIR

a sheen

From the wool of the Angora goat. A long, straight, and very strong fiber that produces a hairy cloth.

Cutting out: use a nap layout, with the fibers brushing down the pattern pieces in the same direction, from neck to hem Seams: plain, neatened with serger or pinking shears

Thread: polyester all-purpose thread

Needle: machine size 14: sharps for hand sewing

Pressing: steam iron on a wool setting; "stroke" the iron over the wool, moving in the direction of the nap

Use for: jackets, coats, men's wear, home goods, knitted mohair yarns for sweaters



TARTAN

An authentic tartan belongs to a Scottish clan, and each has its own unique design that can only be used by that clan. The fabric is made using a twill weave from worsted yarns.

Cutting out: check the design for even/uneven check as it may need a nap layout or even a single layer layout

Seams: plain, matching the pattern and neatened with serger or zigzag stitch

Thread: polyester all-purpose thread Needle: machine size

14; sharps for hand sewing

Pressing: steam iron on a wool setting; may require a pressing cloth, so test first

Use for: traditionally kilts, but these days also skirts, pants, jackets, home goods



TWEED, MODERN

A mix of chunky and nubby wool yarns. Modern tweed is often found in contemporary color palettes as well as plain, and with interesting fibers in the weft such as metallics and paper. It is much favored by fashion designers.

Cutting out: use a nap layout Seams: plain, neatened with serger or zigzag stitch; the fabric is prone to fraving Thread: polyester all-purpose thread
Needle: machine size 14;

sharps for hand sewing **Pressing:** steam iron on
a wool setting; a pressing
cloth may not be required

cloth may not be required **Use for:** jackets, coats; also skirts, dresses, home goods



TWEED. TRADITIONAL

A rough fabric with a distinctive warp and weft, usually in different colors, and often forming a small check pattern. Traditional tweed is associated with the English countryside.


Cutting out: a nap layout is not required unless the fabric features a check

Seams: plain, neatened with serger or zigzag stitch; can also be neatened with pinking shears Thread: polyester all-purpose thread or 100% cotton thread **Needle:** machine size 14;

sharps for hand sewing

Pressing: steam iron on a steam setting; a pressing cloth may not be required

Use for: jackets, coats, skirts, men's wear, home goods



VENETIAN

A wool with a satin weave, making a luxurious, expensive fabric.

Cutting out: use a nap layout **Seams:** plain, neatened with serger or zigzag stitch

Thread: polyester all—purpose thread or 100% cotton thread Needle: machine size 14; sharps for hand sewing Pressing: steam iron on a steam setting with a silk organza cloth to avoid shine; use a seam roll under the seams to prevent them from showing through Use for: jackets, coats, men's wear



WOOL WORSTED

A light and strong cloth, made from good-quality thin, firm filament fibers. Always steam prior to cutting out as the fabric may shrink slightly after having been stretched around a bolt. Cutting out: use a nap layout Seams: plain, neatened with serger or zigzag stitch or Hong Kong finish

all-purpose thread
Needle: machine size 12/14,
depending on fabric; milliner's
or sharps for hand sewing
Pressing: steam iron on
a wool setting, with a pressing
cloth; use a seam roll to prevent
the seam from showing through
Use for: skirts, jackets,
coats, pants

Thread: polyester



Cotton fabrics

One of the most versatile and popular of all fabrics, cotton is a natural fiber that comes from the seed pods, or bolls, of the cotton plant. It is thought that cotton fibers have been in use since ancient times. Today, the world's biggest producers of cotton include the United States, India, and countries in the Middle East. Cotton fibers can be filament or staple, with the longest and finest used for top-quality bed linen. Cotton clothing is widely worn in warmer climates as the fabric will keep you cool.

PROPERTIES OF COTTON

- absorbs moisture well and carries heat away from the body
- · stronger wet than dry
- · does not build up static electricity
- dves well

- prone to shrinkage unless it has been treated
- will deteriorate from mildew and prolonged exposure to sunlight
- · creases easily
- soils easily, but launders well

EYELET

A fine, plain-weave cotton that has been embroidered in such a way as to make small holes. Usually white or a pastel color.

Cutting out: may need layout to place embroidery at hem edge Seams: plain, neatened with serger or zigzag stitch; a French seam can also be used Thread: polyester all-purpose thread

Needle: machine size 12/14; sharps for hand sewing Pressing: steam iron on a cotton setting; a pressing cloth is not required Use for: baby clothes,



CALICO

A plain weave fabric that is usually unbleached and quite stiff. Available in many different weights, from very fine to extremely heavy.

Cutting out: use a regular layout **Seams:** plain, neatened with serger or zigzag stitch

Thread: polyester all-purpose thread

summer skirts, blouses

Needle: machine size 11/14, depending on thickness of thread; sharps for hand sewing Pressing: steam iron on a steam setting; a pressing cloth is not required Use for: toiles (test garments),

home goods



CHAMBRAY

A light cotton that has a colored warp thread and white weft thread. Chambray can also be found as a check or a striped fabric.

Cutting out: use a regular layout **Seams:** plain, neatened with serger or zigzag stitch

Thread: polyester all-purpose thread

Noodle: machine s

Needle: machine size 11; sharps for hand sewing Pressing: steam iron on a cotton setting: a pressing cloth is not required

Use for: blouses, men's shirts, children's wear



CHINTZ

A floral print or plain cotton fabric with a glazed finish that gives it a sheen. It has a close weave and is often treated to resist dirt.

Cutting out: use a nap layout
Seams: plain, neatened with serger or zigzag stitch; a run and

fell seam can also be used

Thread: polyester all-purpose thread or 100% cotton thread Needle: machine size 14; milliner's for hand sewing Pressing: steam iron on a cotton

setting; a pressing cloth may be required due to sheen on fabric

Use for: home goods



CORDUROY

A soft pile fabric with distinctive stripes (known as wales or ribs) woven into it. The name depends on the size of the ribs: baby or pin cord has extremely fine ribs; needle cord has slightly thicker ribs; corduroy has 10-12 ribs per 1in (2.5cm); and elephant or jumbo cord has thick, heavy ribs.

Cutting out: use a nap layout with the pile on the corduroy, brushing the pattern pieces from neck to hem, to give depth

Seams: plain, stitched using a walking foot and neatened with serger or zigzag stitch

Thread: polyester all-purpose thread

Needle: machine size 12/16: sharps or milliner's for hand sewing

Pressing: steam iron on a cotton setting; use a seam roll under the seams with a pressing cloth Use for: pants, skirts, men's wear



CRINKLE COTTON

Looks like an exaggerated version of seersucker (see p36), with creases added by a heat process. Crinkle cotton may require careful laundering as it often has to be twisted into shape when wet to put the creases back in.

Cutting out: a nap layout is not required unless the fabric is printed

Seams: plain, neatened with

serger or zigzag stitch

Thread: polyester all-purpose thread

Needle: machine size 12; milliner's for hand sewing

Pressing: steam iron on a cotton setting; take care not to press out the crinkles

Use for: blouses, dresses. children's wear



DAMASK

A cotton that has been woven on a jacquard loom to produce a fabric usually with a floral pattern in a self color. May have a sheen to the surface. Can also be made of silk or linen.

Cutting out: use a nap layout Seams: plain, neatened with serger or zigzag stitch Thread: polyester all-purpose

thread or 100% cotton thread Needle: machine size 14; sharps for hand sewing

Pressing: steam iron on a cotton setting; a pressing cloth may be required if the fabric has a sheen Use for: home furnishings; colored jacquards for



DENIM

Named after Nîmes in France. A hard-wearing twill-weave fabric with a colored warp and white weft, usually made into jeans. Available in various weights and often mixed with an elastic thread for stretch. Denim is usually blue, but is also available in a variety of other colors.

Cutting out: use a regular layout

Seams: run and fell or top-stitched plain

jackets, skirts

Thread: polyester all-purpose thread with top-stitching thread for detail top-stitching

Needle: machine size 14/16; sharps for hand sewing

Pressing: steam iron on a cotton setting; a pressing cloth should not

be required

Use for: jeans, jackets, children's wear



DRILL

A hard-wearing twill or plainweave fabric with the same color warp and weft. Drill frays badly on the cut edges.

Cutting out: use a regular layout Seams: run and fell; or plain, neatened with serger or ziqzag stitch **Thread:** polyester all-purpose thread with top-stitching thread for detail top-stitching **Needle:** machine size 14; sharps for hand sewing

Pressing: steam iron on a cotton setting; a pressing cloth is not required

Use for: men's wear, casual jackets, pants




GINGHAM

A fresh, two-color cotton fabric that features checkers of various sizes. A plain weave made by having groups of white and colored warp and weft threads. Cutting out: usually an even check, so nap layout is not required but recommended; pattern will need matching Seams: plain, neatened with

serger or zigzag stitch

Thread: polyester all-purpose thread Needle: machine size 11/12; sharps for hand sewing Pressing: steam iron on a cotton setting: a pressing cloth should not be required Use for: children's wear, dresses, shirts, home furnishings



JERSEY

A fine cotton yarn that has been knitted to give stretch, making the fabric very comfortable to wear. Jersey will also drape well.

Cutting out: a nap layout is recommended

Seams: 4-thread serger stitch; or plain seam stitched with a small zigzag stitch and then seam allowances stitched together with a zigzag

Thread: polyester all-purpose thread

Needle: machine size 12/14; a ballpoint needle may be required for serger and for hand sewing Pressing: steam iron on a wool setting as jersey may shrink on

a cotton setting **Use for:** underwear, drapey
dresses, leisurewear, bedding

MADRAS

A plaid fabric made from a fine cotton yarn, usually from India. Often found in bright colors. An inexpensive cotton fabric.

Cutting out: use a nap layout and match the pattern

Seams: plain, neatened with serger or zigzag stitch Thread: polyester all-purpose thread Needle: machine size 12/14; sharps for hand sewing Pressing: steam iron on a cotton setting; a pressing cloth is not required

Use for: shirts, skirts, home

furnishings



MUSLIN

A fine, plain, open-weave cotton. Can be found in colors but usually sold a natural/unbleached or white. Makes great pressing cloths and interlinings. It is a good idea to wash prior to use.

Cutting out: use a regular layout Seams: 4-thread serger stitch; or plain seam, neatened with serger or zigzag stitch; a French seam could also be used

Thread: polyester all-purpose thread

Needle: machine size 11; milliner's for hand sewing

Pressing: steam iron on a cotton setting: a cloth is not required Use for: curtaining and other

household uses, as well as test

patterns or toiles

SEERSUCKER

A woven cotton that has a bubbly appearance woven into it, due to stripes of puckers. Do not over-press, or the surface effect will be damaged.

Cutting out: use a nap layout, due to puckered surface effect
Seams: plain, neatened with serger or zigzag stitch

Thread: polyester all-purpose thread

Needle: machine size 11/12; milliner's for hand sewing

Pressing: steam iron on a cotton setting (be careful not to press out the wrinkles)

Use for: summer clothing, skirts, shirts, children's wear

SHIRTING

A closely woven, fine cotton, with colored warp and weft yarns making stripes or checks.

Cutting out: use a nap layout if fabric has uneven stripes Seams: plain, neatened with serger or zigzag stitch; a run and fell seam can also be used Thread: polyester all-purpose thread

Needle: machine size 12; milliner's for hand sewing

Pressing: steam iron on a cotton setting; a pressing cloth

is not required

Use for: ladies' and men's shirts

TERRY CLOTH

A cotton fabric with loops on the surface; top-quality terry cloth has loops on both sides. It is highly absorbent. Wash before use to preshrink and make it fluffy.

Cutting out: use a nap layout Seams: 4-thread serger stitch; or plain seam, neatened with serger or zigzag stitch Thread: polyester all-purpose thread

Needle: machine size 14; sharps for hand sewing Pressing: steam iron on

a cotton setting; a pressing cloth is not required

Use for: bathrobes, beachwear, towels

VELVET

A pile-weave fabric, made by using an additional yarn that is then cut to produce the pile. Difficult to handle and can be easily damaged if seams have to be unpicked.

Cutting out: use a nap layout with the pile brushing up from hem to neck, to give depth of color Seams: plain, stitched using

a walking foot (stitch all seams

from hem to neck) and neatened with serger or zigzag stitch

Thread: polyester all-purpose thread Needle: machine size 14; milliner's for hand sewing

Pressing: only if you have to; use a velvet board, a bit of steam, toe of iron, and silk organza cloth

Use for: jackets, coats





Silk fabrics

Often referred to as the queen of all fabrics, silk is made from the fibers of the silkworm's cocoon. This strong and luxurious fabric dates back thousands of years to its first development in China, and the secret of silk production was well protected by the Chinese until 300AD. Silk fabrics can be very fine or thick and chunky. They need careful handling as some silk fabrics can be easily damaged.

PROPERTIES OF SILK

- · keeps you warm in winter and cool in summer
- absorbs moisture and dries quickly
- dyes well, producing deep, rich colors
- static electricity can build up and fabric may cling
- will fade in prolonged strong sunlight

- · prone to shrinkage
- · best dry-cleaned
- weaker when wet than dry
- · may water-mark

CHIFFON

A very strong and very fine, transparent silk with a plain weave. Will gather and ruffle well. Difficult to handle.

Cutting out: place tissue paper under the fabric and pin the fabric to the tissue, cutting through all layers if necessary; use extra-fine pins

Seams: French
Thread: polyester
all-purpose thread
Needle: machine size G

Needle: machine size 9/11; fine milliner's for hand sewing **Pressing:** dry iron on

a wool setting

Use for: special-occasion wear,

over-blouses

CREPE DE CHINE

Medium weight, with an uneven surface due to the twisted silk yarn used. Drapes well and often used on bias-cut garments.

Cutting out: if to be bias-cut, use a single layer layout; otherwise use a nap layout

Seams: if to be bias-cut, use

a single layer layout; otherwise use a nap layout

Thread: polyester all-purpose thread

Needle: machine size 11; milliner's or betweens for hand sewing **Pressing:** dry iron on a wool setting

Use for: blouses, dresses, special-occasion wear

DUCHESS SATIN

A heavy, expensive satin fabric used almost exclusively for special-occasion wear.

Cutting out: use a nap layout Seams: plain, with pinked edges

Thread: polyester all-purpose thread

Needle: machine size 12/14; milliner's for hand sewing **Pressing:** steam iron on a wool

setting with a pressing cloth; use a seam roll under the seams to prevent shadowing

Use for: special-occasion wear

DUPIONI

Similar to shantung (see page 38) but woven using a much smoother yarn to reduce the amount of nubbly bits in the weft.

Cutting out: use a nap layout to prevent shadowing

Seams: plain, neatened with serger or zigzag stitch

Thread: polyester all-purpose thread

Needle: machine size 12; milliner's for hand sewing

Pressing: steam iron on a wool setting, with a pressing cloth as fabric may water-mark

Use for: dresses, skirts, jackets, special-occasion wear, home goods

SHANTUNG

The most popular of all the silks. A distinctive weft yarn with many nubbly bits. Available in hundreds of colors. Easy to handle, but it does fray badly.

Cutting out: use a nap layout as the fabric shadows Seams: plain, neatened with serger or zigzag stitch Thread: polyester all-purpose thread Needle: machine size 12; milliner's for hand sewing

Pressing: steam iron on a wool setting, with a pressing cloth to avoid water-marking

Use for: dresses, special-occasion wear, jackets, home goods



GEORGETTE

A soft, filmy silk fabric that has a slight transparency. Does not crease easily.

Cutting out: place tissue paper under the fabric and pin fabric to tissue, cutting through all layers if necessary; use extra-fine pins Seams: French Thread: polyester all-purpose thread

Needle: machine size 11; milliner's for hand sewing Pressing: dry iron on a wool setting to avoid damage by steam Use for: special-occasion wear, loose-fitting overshirts

HABUTAI

Originally from Japan, a smooth, fine silk that can have a plain or a twill weave. Fabric is often used for silk painting.

Cutting out: use a regular layout Seams: French

Thread: polyester all-purpose thread

Needle: machine size 9/11; very fine milliner's or betweens for hand sewing

Pressing: steam iron on a wool setting

Use for: lining, shirts, blouses

MATKA

A silk suiting fabric with an uneven-looking yarn. Matka can be mistaken for linen.

Cutting out: use a nap layout as silk may shadow


Seams: plain, neatened with serger or zigzag stitch or Hong Kong finish

Thread: polyester all-purpose thread

Needle: machine size 12/14; milliner's for hand sewing Pressing: steam iron on a wool setting with a pressing cloth; a seam roll is recommended

a seam roll is recommended to prevent the seams from showing through

Use for: dresses, jackets, pants



ORGANZA

A sheer fabric with a crisp appearance that will crease easily.

Cutting out: use a regular layout Seams: French or a seam for

a difficult fabric **Thread:** polyester
all-purpose thread

Needle: machine size 11; milliner's or betweens for hand sewing

Pressing: steam iron on a wool setting; a pressing cloth should not be required

Use for: sheer blouses, shrugs, interlining, interfacing

SATIN

A silk with a satin weave that can be very light to quite heavy in weight.

Cutting out: use a nap layout in a single layer as fabric is slippery

Seams: French; on thicker satins, a seam for a difficult fabric

Thread: polyester all-purpose thread (not silk thread as it becomes weak with wear)

Needle: machine size 11/12; milliner's or betweens for hand sewing

Pressing: steam iron on a wool setting, with a pressing cloth as fabric may water-mark Use for: blouses, dresses, special-occasion wear

SILK AND WOOL BLEND

A fabric made by mixing wool and silk fibers or wool and silk yarns. The fabric made may be fine in quality or thick, like a coating. Cutting out: use a nap layout Seams: plain, neatened with serger or zigzag stitch Thread: polyester

Needle: machine size 11/14, depending on fabric; sharps for hand sewing

Pressing: steam iron on a wool setting; seams will require some steam to make them lie flat Use for: suits, skirts, pants, coats



TAFFETA

all-purpose thread

A smooth, plain-weave fabric with a crisp appearance. It makes a rustling sound when worn. Can require special handling and does not wear well.

Cutting out: use a nap layout, with extra-fine pins in seams as they will mark the fabric

Seams: plain; fabric may pucker, so sew from the hem upward, keeping the fabric taut under the machine; neaten with serger or pinking shears

Thread: polyester all-purpose thread

Needle: machine size 11; milliner's or betweens for hand sewing Pressing: cool iron, with a seam roll under the seams

Use for: special-occasion wear

Linen fabrics

Linen is a natural fiber that is derived from the stem of the flax plant. It is available in a variety of qualities and weights, from very fine linen to heavy suiting weights. Coarser than cotton, it is sometimes woven with cotton as well as being mixed with silk.

PROPERTIES OF LINEN

- cool and comfortable to wear
- · absorbs moisture well
- · shrinks when washed
- · does not ease well
- has a tendency to wrinkle
- prone to fraying
- resists moths but is damaged by mildew

COTTON AND LINEN BLEND

Two fibers may have been mixed together in the yarn or may have mixed warp and weft yarns. It has lots of texture in the weave. Silk and linen mix is treated in the same way.

Cutting out: use a regular layout **Seams:** plain, neatened with serger or zigzag stitch

Thread: polyester all-purpose thread

Needle: machine size 14; sharps for hand sewing **Pressing:** a steam iron on

a steam setting, with a silk organza pressing cloth **Use for:** summer-weight

Use for: summer-weight jackets, tailored dresses

DRESS-WEIGHT LINEN

A medium-weight linen with a plain weave. The yarn is often uneven, which causes slubs in the weave.

Cutting out: use a regular layout. Seams: plain, neatened with serger or zigzag stitch or a Hong Kong finish Thread: polyester all-purpose thread with a top-stitching thread for top-stitching Needle: machine size 14; sharps for hand sewing Pressing: steam iron on

a cotton setting **Use for:** dresses, pants, skirts

PRINTED LINENS

Many linens today feature prints or even embroidery. The fabric may be light to medium weight, with a smooth yarn that has few slubs.

Cutting out: use a nap layout **Seams:** plain, neatened with serger or zigzag stitch

Thread: polyester all-purpose thread Needle: machine size 14; sharps for hand sewing Pressing: steam iron on a cotton setting (steam is required to remove creases)

Use for: dresses, skirts

SUITING LINEN

A heavier yarn is used to produce a linen suitable for suits for men and women. Can be a firm, tight weave or a looser weave.

Cutting out: use a regular layout **Seams:** plain, neatened with serger or a zigzag stitch and sharps for hand-sewing needle

Thread: polyester all-purpose thread with a top-stitch thread for top-stitching Needle: machine size 14; sharps for hand sewing Pressing: steam iron on a cotton setting (steam is required to remove creases) Use for: men's and women's suits, pants, coats





Leather and suede

Leather and suede are natural fabrics derived from either a pig or a cow and are sold as skins. Depending on the curing process that has been used, the skin will be either a suede or a leather. The fabrics require special handling.

LEATHER AND SUEDE

As the pattern pieces cannot be pinned on to leather and suede, you will need to draw around them using tailor's chalk. After cutting out, the chalk will rub off and will not damage the skin. Cutting out: a complete

pattern is required, left

and right-hand halves; usea nap layout for suede, as it will brush one way Seams: lapped or plain, using a walking foot or an ultra glide foot; neatening is not required

Thread: polyester all-purpose thread Needle: machine size 14 (a special leather needle may actually damage the skin); hand sewing is not recommended

Pressing: Avoid steam when ironing; set the iron on the rayon setting and use a 100% cotton cloth between the iron and leather

Use for: skirts, pants, jackets, home goods



Manmade fabrics

The term "manmade" applies to any fabric that is not 100 percent natural. Many of these fabrics have been developed over the last hundred years, which means they are new compared to natural fibers. Some manmade fabrics are made from natural elements mixed with chemicals while others are made entirely from non-natural substances.

ACETATE

Introduced in 1924, acetate is made from cellulose and chemicals. The fabric has a slight shine and is widely used for linings. Acetate can also be woven into fabrics such as acetate taffeta, acetate satin, and acetate jersey.

Properties of acetate:

- · dves well
- can be heat-set into pleats
- washes well

Cutting out: use a nap layout due to sheen on fabric Seams: plain, neatened with serger or zigzag stitch, or 4-thread serger stitch Thread: polyester all-purpose thread

Needle: machine size 11;

sharps for hand sewing **Pressing:** steam iron on
a cool setting (fabric can melt) **Use for:** special-occasion

wear, linings

ACRYLIC

Introduced in 1950, acrylic fibers are made from ethylene and acrylonitrile. The fabric resembles wool and makes a good substitute for machine-washable wool. Often seen as a knitted fabric, the fibers can be mixed with wool.

Properties of acrylic:

- little absorbency
- · tends to retain odors
- not very strong

Cutting out: use a regular layout **Seams:** 4-thread serger stitch on knitted fabrics; plain seam on woven fabrics

Thread: polyester all-purpose thread

Needle: machine size 12/14, but a ballpoint needle may be required on knitted fabrics; sharps for hand sewing

Pressing: steam iron on a wool setting (fabric can be damaged by heat)

Use for: knitted yarns for sweaters; wovens for skirts, blouses



NYLON

Developed by DuPont in 1938, the fabric takes its name from a collaboration between New York (NY) and London (LON). Nylon is made from polymer chips that are melted and extruded into fibers. The fabric can be knitted or woven.

Properties of nylon:

serger or zigzag stitch

- very hard-wearing
- · does not absorb moisture
- washes easily, although white nylon can discolor easily
- very strong

Cutting out: a nap layout is not required unless the fabric is printed **Seams:** plain, neatened with

Thread: polyester all-purpose thread

Needle: machine size 14, but a ballpoint needle may be required for knitted nylons; sharps for hand sewing

Pressing: steam iron on a silk setting (fabric can melt)
Use for: sportswear, underwear

POLYESTER

One of the most popular of the manmade fibers, polyester was introduced in 1951 as a washable man's suit. Polyester fibers are made from petroleum by-products and can take on any form, from a very fine sheer fabric to a thick, heavy suiting.

Properties of polyester:

- · non-absorbent
- does not crease
- can build up static
- may "pill"

Cutting out: a nap layout is only required if the fabric is printed Seams: French, plain, or 4-thread serger, depending on the weight of the fabric

Thread: polyester all-purpose thread

Needle: machine size 11/14; sharps for hand sewing

Pressing: steam iron on a polyester setting

Use for: workwear, school uniforms

RAYON

Also known as viscose and often referred to as artificial silk, this fiber was developed in 1889. It is made from wood pulp or cotton linters mixed with chemicals. Rayon can be knitted or woven and made into a wide range of fabrics. It is often blended with other fibers.

Properties of rayon:

- is absorbent
- is not static
- · dyes well
- frays badly

Cutting out: a nap layout is only required if the fabric is printed Seams: plain, neatened with serger or zigzag stitch Thread: polyester all-purpose thread

Needle: machine size 12/14; sharps for hand sewing **Pressing:** steam iron on

a silk setting

Use for: dresses, blouses, jackets



SPANDEX

Introduced in 1958, this is a lightweight, soft fiber than can be stretched 500% without breaking. A small amount of spandex is often mixed with other fibers to produce wovens with a slight stretch.

Properties of spandex:

- resistant to body oils, detergents, sun, sea, and sand
- can be difficult to sew
- · can be damaged by heat
- not suitable for hand sewing

Cutting out: use a nap layout Seams: 4-thread serger stitch or a seam stitched with a small zigzag Thread: polyester all-purpose thread

Needle: machine ballpoint size 14 or a machine stretch needle

Pressing: steam iron on a wool setting (spandex can be damaged by a hot iron)

Use for: swimwear, foundation wear, sportswear



SYNTHETIC FURS

Created using a looped yarn that is then cut on a knitted or a woven base, synthetic fur can be made from nylon or acrylic fibers. The furs vary tremendously in quality and some are very difficult to tell from the real thing.

Properties of synthetic furs:

- · require careful sewing
- can be heat-damaged by pressing
- not as warm as real fur
 Cutting out: use a nap layout, with the fur pile brushed from the neck to the hem; cut just the backing carefully and not through the fur pile

Seams: plain, with a longer stitch

and a walking foot; no neatening is required

Thread: polyester all-purpose thread

Needle: machine size 14;

sharps for hand sewing

Pressing: if required, use a cool
iron (synthetic fur can melt under
a hot iron)

Use for: outerwear



SYNTHETIC LEATHER AND SUEDE

Made from polymers, these are non-woven fabrics. Some synthetic leathers and suedes can closely resemble the real thing.

Properties of synthetic leather and suede:

- · do not fray
- do not ease well
- can be difficult to sew by hand, so this is not recommended

Cutting out: use a nap layout Seams: plain, stitched using a walking foot and neatened with pinking shears; can also use top-stitched seams and lapped seams Thread: polyester all-purpose thread

Needle: machine size 11/14 Pressing: steam iron on a wool setting, with a pressing cloth Use for: jackets, skirts, pants,

home goods



Fabric construction

Most fabric is made by either knitting or weaving. A knitted fabric is constructed by interlocking looped yarns. For a woven fabric, horizontal and vertical yarns go under and over each other. The warp yarn, which is the strongest, runs vertically and the weft crosses it at right angles. There are also non-woven fabrics created by a felting process where tiny fibers are mixed and squeezed together, then rolled out.

PLAIN WEAVE

As the name suggests, this is the simplest of all the weaves. The weft yarn passes under one warp yarn, then over another one.

SATIN WEAVE

This has a long strand known as a float on the warp yarn. The weft goes under four warp yarns, then over one. This weave gives a sheen on the fabric.

HERRINGBONE WEAVE

The distinctive herringbone zigzag weave is made by the weft yarn going under and over warp yarns in a staggered pattern.

TWILL WEAVE

The diagonal twill weave is made by the weft yarn going under two warp yarns, then over another two, with the pattern moved one yarn across each time.

WARP KNIT

This is made on a knitting machine, where one yarn is set to each needle (latch). The knit is formed in a vertical and diagonal direction.

WEFT KNIT

Made in the same way as knitting by hand on needles, this uses one yarn that runs horizontally.



Interfacings

An interfacing is a piece of fabric that is attached to the main fabric to give it support or structure. An interfacing fabric may be woven, knitted, or non-woven. It may also be fusible or non-fusible. A fusible interfacing (also called iron-on) can be bonded to the fabric by applying heat, whereas a non-fusible interfacing needs to be sewn to the fabric with a basting stitch. Always cut interfacings on the same grain as the fabric, regardless of its construction.

Fusible interfacings

Be sure to buy fusibles designed for the home sewer, because the adhesive on the back of fusible interfacings for commercial use cannot be released with a normal steam iron. Do all pattern markings after the interfacing has been applied to the fabric.

HOW TO APPLY A FUSIBLE INTERFACING



- Place fabric on pressing surface, wrong side up, making sure it is straight and not wrinkled.
- Place the chosen interfacing sticky side down on the fabric (the sticky side feels gritty).
- Cover with a dry pressing cloth and spray the cloth with a fine mist of water.
- Place a steam iron, on a steam setting, on top of the pressing cloth.

- Leave the iron in place for at least 10 seconds before moving it to the next area of fabric.
- Check to see if the interfacing is fused to the fabric by rolling the fabric—if the interfacing is still loose in places, repeat the pressing process.
- When the fabric has cooled down, the fusing process will be complete. Then pin the pattern back on to the fabric and transfer the pattern markings as required.

WOVEN

A woven fusible is always a good choice for a woven fabric as the two weaves will work together. Always cut on the same grain as the fabric. This type of interfacing is suitable for crafts and for more structured garments.

LIGHTWEIGHT WOVEN

A very light, woven fusible that is almost sheer, this can be difficult to cut out as it tends to stick to the scissors. It is suitable for all light to medium-weight fabrics.

KNITTED

A knitted fusible is ideally suited to a knit fabric as the two will be able to stretch together. Some knitted fusibles only stretch one way, while others will stretch in all directions. A knitted fusible is also a good choice on fabrics that have a percentage of stretch.


NON-WOVEN

Non-woven fusibles are available in a wide variety of weights—choose one that feels lighter than your fabric. You can always add a second layer if one interfacing proves to be too light. This interfacing is suitable for supporting collars and cuffs, and facings on garments.

Non-fusible interfacings

These sew-in interfacings require basting to the wrong side of facings or the main garment fabric around the seam allowances. They are useful for sheer or fine fabrics where the adhesive from a fusible interfacing might show through.

HOW TO APPLY A NON-FUSIBLE INTERFACING



Place the interfacing on to the wrong side of the fabric, aligning the cut edges.

Pin in place.

Using a basting stitch, baste the interfacing to the fabric at ³/₆in (1cm) within the seam allowance.

ALPACA

A tailorings canvas made from wool and alpaca, this interfacing is excellent to use in difficult fabrics such as velvet, because the alpaca can be steamed into shape.



CANVAS

A firm, white cotton, this will stiffen shirt collars and also boned bodices. It is available as firm and soft collar canvas although there is little difference between the two. Collar canvas is also useful in crafts, such as handbags.

MUSLIN


A cotton muslin interfacing is a good choice on summer dresses as well as for special-occasion wear. Muslin can also be used to line fine cotton dresses.

ORGANZA

A pure silk organza makes an excellent interfacing for sheer fabric to give support and structure. It can also be used for structure in much larger areas such as bridal skirts.

NON-WOVEN SEW-IN INTERFACING

A non-woven material is ideal for crafts and small areas of garments, such as cuffs and collars. Use it in garments when a woven or fusible alternative is not available.



STITCH ESSENTIALS

Hand sewing


It is necessary to use hand sewing to prepare the fabric prior to permanent stitching—these temporary basting stitches will eventually be removed. Permanent hand sewing is used to finish a garment and to attach fasteners, as well as to help out with a quick repair.

Threading the needle


When sewing by hand, cut your piece of thread to be no longer than the distance from your fingertips to your elbow.

If the thread is much longer than this, it will knot as you sew.


HOW TO THREAD A NEEDLE



Hold your needle in your right hand and the end of the thread in your left. Keeping the thread still, place the eye of the needle over the thread.



If the needle will not slip over the thread, dampen your fingers and run the moisture across the eye of the needle. Pull the thread through.



At the other end of the thread, tie a knot as shown or secure the thread as shown opposite.




You are now ready to start your sewing.

Securing the thread

The ends of the thread must be secured firmly, especially if the hand sewing is to be permanent. A knot (see opposite page) is frequently used and is the preferred choice for temporary stitches. For permanent sewing, a double stitch is a better option.

DOUBLE STITCH




Take a stitch.


2 Go back through the stitch with the thread wrapped under the needle.

Pull through to make a knot.

BACK STITCH



LOCKING STITCH



Basting stitches


Each of the many types of basting stitches has its own individual use. Basic bastes hold two or more pieces of fabric together. Long and short bastes are an alternative version of the basic basting stitch, often used when the basting will stay in the work for some time. Diagonal bastes hold folds or overlaid fabrics together, while slip bastes are used to hold a fold in fabric to another piece of fabric.

BASIC BASTES



Starting with a knot and, using single thread, make straight stitches, evenly spaced.

LONG AND SHORT



Make long stitches with a short space between each one.

DIAGONAL BASTES



Work vertically, taking horizontal stitches.

SLIP BASTES




Take a stitch into the fold and then a stitch into the base fabric.

Stitches for hand sewing


There are a number of hand stitches that can be used during construction of a garment or other item. Some are for decorative purposes while others are more functional.

BACK STITCH




A strong stitch that could be used to construct a piece of work. Work from right to left. Bring the needle up, leaving a space, and then take the thread back to the end of the last stitch.

RUNNING STITCH




Very similar to basting (see page 49), but used more for decorative purposes. Work from right to left. Run the needle in and out of the fabric to create even stitches and spaces.

WHIP STITCH




A diagonal stitch sewn with a single thread along a raw edge to prevent fraying. Work from right to left. Take a stitch through the edge of the fabric. The depth of the stitch depends on the thickness of the fabric—for a thin fabric, take a shallow stitch.

BUTTONHOLE STITCH



Used to make hand-worked buttonholes and also to secure fastenings. It is always stitched on an edge with no spaces between the stitches. Work from right to left. Push the needle from the top edge into the fabric.




Wrap the thread behind the needle as the needle goes in and again as the needle leaves the fabric. Pull through and a knot will appear at the edge. This is an essential stitch for all sewers and is not difficult to master.

50


Stitch essentials

HERRINGBONE STITCH




A very useful stitch as it is secure yet has some movement in it. It is used to secure hems and interlinings. Work from left to right. Take a small (not more than 0.5mm) horizontal stitch into one layer and then the other, so the thread crosses itself.

FLAT FELL STITCH



A strong, secure stitch to hold two layers permanently together. This stitch is often used to secure bias bindings and linings. Work from right to left. Make a short, straight stitch at the edge of the fabric.

SLIP HEM STITCH



Also called a catch stitch, this is used primarily for securing hems. It looks similar to herringbone (above). Work from right to left. Take a short horizontal stitch into one layer and then the other.

BLIND HEM STITCH




As the name suggests this is for hemming a garment. As the stitch is under the edge of the fabric it should be discreet. Work from right to left and use a slip hem stitch (left).

BLANKET STITCH



Similar to buttonhole stitch but without the knot. Blanket stitch is useful to neaten edges and for decorative purposes. Always leave a space between the stitches. Push the needle into the fabric and, as it appears at the edge, wrap the thread under the needle.

CROSS STITCH



A temporary securing stitch used to hold pleats in place after construction. It can also be used to secure linings. Work a row of even diagonal stitches in one direction and then a row back over them to make crosses.

Machine sewing and seams

Fabric is joined together using seams—whether it be for an item of clothing, craft work, or home goods. The most common seam is a plain seam, which is suitable for a wide variety of fabrics and items. However, there are many other seams to be used as appropriate, depending on the fabric and item being constructed. Some seams are decorative and can add detail to structured garments.


Securing the thread REVERSE STITCH LOCKING STITCH Machine stitches need to be secured at the end of When starting. When starting. a seam to prevent them from coming undone. This can sew a couple press the be done by hand, tying the ends of the thread, or using of stitches locking stitch the machine with a reverse stitch or a locking stitch, forward, then and stitch, then which stitches three or four stitches in the same place. continue forward. hold in the reverse button TIE THE ENDS and reverse over them. Continue forward again. Pull on the top Pull the loop At the end of At the end of thread and it will through to threads together. the seam. the seam. pull up a loop—this the top. reverse again to press the locking

Stitches made with a machine

The sewing machine will sew plain seams and decorative seams as well as buttonholes of various styles. The length and width of all buttonholes can be altered to suit the garment or craft item.

secure the stitches.

stitch again.




Used for most applications. The length of the stitch can be altered from 0.5 to 5.0 and decorative purposes. Both the width and the length of this stitch can be altered.

To neaten seam edges and for securing and decorative purposes. Both the width stitch is decorative as well as functional, and is often found in lingerie. The stitch length and width can be altered.

is the bobbin thread.

BLIND HEM STITCH



Made in conjunction with the blind hem foot. A combination of straight stitches and a zigzag stitch (see opposite page). Used to secure hems.

OVEREDGE STITCH



Made in conjunction with the overedge foot. The stitch is used for neatening the edge of fabric. The width and length of the stitch can be altered.

STRETCH STITCH



Also known as a lightening stitch. This stitch is recommended for stretch knits, but is better used to help control difficult fabrics.

BASIC BUTTONHOLE STITCH



Square on both ends. Used on all styles of garment.

ROUND-END BUTTONHOLE STITCH




One square end and one round end. Used on jackets.

KEYHOLE BUTTONHOLE STITCH





One square end and one end shaped like a loop. Used on jackets.

DECORATIVE STITCHES




Sewing machines are capable of producing decorative linear stitches. These can be used to enhance the surface of work or a seam as they add interest to edges. Or, when worked as many rows together, they can be used to create a piece of embroidered fabric.





How to make a plain seam

A plain seam is 5% in (1.5cm) wide. It is important that the seam is sewn accurately at this measurement, otherwise the item being made will come out the wrong size and shape. There are guides on the plate of the sewing machine that can be used to help align the fabric.



Seam neatening


It is important that the raw edges of the seam are neatened or finished—this will make the seam hard-wearing and prevent fraying. The method of neatening will depend on the style of item that is being made and the fabric you are using.

PINKED




This method of neatening is ideal to use on fabrics that do not fray badly. Using pinking shears, trim as little as possible off the raw edge.

ZIGZAGGED




All sewing machines will make a zigzag stitch. It is an ideal stitch to use to stop the edges from fraying and is suitable for all types of fabric. Sew in from the raw edge, then trim back to the zigzag stitch. On most fabrics, use a stitch width of 2.0 and a stitch length of 1.5.

OVEREDGE SEWING



This is found on most sewing machines. Select the overedge stitch on your machine. Using the overedge machine foot and the pre-set stitch length and width, machine along the raw edge of the seam.


CLEAN FINISHED



This is a very hard-wearing finish and is ideal for cottons and fine fabrics. Using a straight stitch, turn under the raw edge of the seam allowance by ½in (3mm) and sew straight along the fold.

Hong Kong finish

This is a great finish to use on wools and linens, to neaten the seams on unlined jackets. It is made by wrapping the raw edge with bias-cut strips.





Wrap to the wrong side of the raw edge, with the raw edge of the bias strip against the sewn seam.



Pin the wrapped bias strip to the fabric, then press the folded edge.





Machine sew the wrapped bias strip to the seam, from the upper side of the seam, sewing alongside the edge of the bias.

Sewing corners and curves

Not all sewing is straight lines. The work will have curves and corners that require negotiation, to produce sharp, clean angles and curves on the right side. The technique for sewing a corner shown below applies to corners of all angles. On a thick fabric, the technique is slightly different, with a stitch taken across the corner, and on a fabric that frays badly the corner is reinforced with a second line of stitches.


SEWING A CORNER








SEWING A CORNER ON HEAVY FABRIC



SEWING A REINFORCED CORNER






SEWING AN INNER CORNER

Sew accurately at 5/sin (1.5cm) from the edge, pivoting at the comer (see Sewing a comer, steps 3–5, page 57). Clip through the seam allowance into the corner.

SEWING AN INNER CURVE



SEWING AN OUTER CURVE



Reducing seam bulk

It is important that the seams used for construction do not cause bulk on the right side. To make sure this does not happen, the seam allowances need to be reduced in size by a technique known as layering a seam. They may also require V shapes to be removed, which is known as notching, or the seam allowance may be clipped.

Layering a seam

On the majority of fabrics, if the seam is on the edge of the work, the fabric in the seam needs reducing. The seam allowance closest to the outside of the garment or item stays full width, while the seam allowance closest to the body or inside is reduced.




Cut along one side of the seam to reduce the fabric in the seam allowance by half to one-third of its original width.

Reducing seam bulk on an inner curve

For an inner curve to lie flat, the seam will need to be layered and notched, then understitched to hold it in place (see page 60).








Turn to the right



Understitch the seam

Reducing seam bulk on an outer curve

An outer curve also needs layering and notching or clipping to allow the fabric to turn to the right side, after which it is understitched.








: Clip through the seam allowances to reduce bulk.



_____ Turn through to the right side and press.





Sewn finishes

Top-stitching and understitching are two methods to finish edges. Top-stitching is meant to be seen on the right side of the work, whereas understitching is not visible from the right side.

TOP-STITCHING



A top-stitch is a decorative, sharp finish to an edge. Use a longer stitch length, of 3.0 or 3.5, and machine on the right side of the work, using the edge of the machine foot as a guide.

UNDERSTITCHING




Understitching is used to secure a seam that is on the edge of a piece of fabric. It helps to stop the seam from rolling to the right side. First make the seam, then layer, turn, and press on to the right side. Open the seam again and push the seam allowance over the layered seam allowance. Sew the seam allowance down.

60

Stitch essentials


French seam

A French seam is a seam that is sewn twice, first on the right side of the work and then on the wrong side, enclosing the first seam. The French seam has traditionally been used on delicate garments such as lingerie and on sheer and silk fabrics.




Flat fell seam

Some garments require a strong seam that will withstand frequent washing and wear and tear. A flat fell seam is very strong. It is made on the right side of a garment and is used on the inside leg seam of jeans, and on men's tailored shirts.




Top-stitch seam

A top-stitch seam is very useful as it is both decorative and practical. This seam is often used on crafts and home goods as well as garments.



Lapped seam

Also called an overlaid seam, a lapped seam is constructed on the right side of the garment. It is a very flat seam when it is finished.




62

Seams on difficult fabrics

Some fabrics require special care for seam construction because they are very bulky, as you find with a fur fabric, or so soft and delicate that they appear too soft to sew. On a sheer fabric, the seam used is an alternative to a French seam; it is very narrow when finished and presses very flat. Making a seam on suede is done by means of a lapped seam. As some suede-effect fabric has a fake fur on the other side, the seam is reversible.

A SEAM ON SHEER FABRIC







Sew again ³/₁₆in (5mm) from the first line of stitches, using either a very narrow zigzag stitch or a stretch stitch. Press.

Trim the raw edge of the fabric close to the second row of stitches.

A SEAM ON SUEDE OR SUEDE-EFFECT FABRIC




Overlap one side of the seam over the other, matching the 5/kin (1.5cm) baste lines. The raw edge should touch the second row of bastes.....



Using a walking foot and a longer than normal stitch length of 3.5, sew the two layers together along the bastes marking the 5/sin (1.5cm) seam allowance.





A SEAM ON FUR FABRIC




Pin the fabric together right side to right side, placing the pins in alternate directions to stop the fur moving.





3 Finger press the seam open.

Trim the surplus fur fabric off the seam allowances.




PATTERNS

Reading patterns

A pattern has three main components: the envelope, the pattern, and the instructions. The envelope gives an illustration of the item together with fabric suggestions and requirements. The pattern sheets inside the envelope are normally printed on tissue paper and contain a wealth of information, while the instructions tell you how to construct the item.


Reading a pattern envelope

The envelope front illustrates the finished garment or item. The different versions are known as views. On the reverse of the envelope, there is usually an illustration of the back view and the standard body measurement chart that has been used for this pattern, plus a chart that will help you purchase the correct amount of fabric for each view.




Single-size patterns

Some patterns contain a garment or craft project of one size only. If you are using a single-size pattern, cut around the tissue on the thick black cutting line before making any alterations.



front armhole and double on back armhole

Dart cutting line:




Positions and number of notches on both sides should match to ensure correct edges are joined together

Open dart is very wide, and fabric is cut away with pattern following cutting line


Multi-size patterns

Many patterns today have more than one size printed on the tissue. Each size is clearly labeled and the cutting lines are marked with a different type of line for each size.



Pattern markings

Each pattern piece will have a series of lines, dots, and other symbols printed on it. These symbols are to help you alter the pattern and join the pattern pieces together.



Body measuring

Accurate body measurements are needed to determine the correct pattern size to use and if any alterations are required. Pattern sizes are usually chosen by the hip or bust measurement; for tops follow the bust measurement, but for skirts or pants use the hip measurement. If you are choosing a dress pattern, go by whichever measurement is the largest.

TAKING BODY MEASUREMENTS

- You'll need a tape measure and ruler as well as a helper for some of the measuring, and a hard chair or stool.
- Wear close-fitting clothes such as a leotard and leggings.
- Do not wear any shoes.

CHEST

Measure above the bust, high under the arms, keeping the tape measure flat and straight across the back.



HOW TO MEASURE YOUR HEIGHT

Most paper patterns are designed for a woman 5ft 5in to 5ft 6in (165 to 168cm). If you are shorter or taller than this you may need to adjust the pattern prior to cutting out your fabric.

Remove your shoes.

Stand straight, with your back against the wall.

 $\label{eq:place} \begin{subarray}{ll} \begin{suba$

A Step away and measure the distance from the floor to the marked point.

FULL BUST

Make sure you are wearing a good-fitting bra and measure over the fullest part of the bust. If your cup size is in excess of a B, you will probably need to do a bust alteration, although some patterns are now cut to accommodate larger cup sizes.



WAIST

This is the measurement around the smallest part of your waist. Wrap the tape around first to find your natural waist, then measure.



HIPS

This measurement must be taken around the fullest part of the hips, between the waist and legs.



BACK WAIST

Take this measurement down the center of the back, from the lumpy bit at the top of the spine, in line with the shoulders, to the waist.



HIGH HIP

Take this just below the waist and just above the hip bones to give a measurement across the tummy.



OUTSIDE LEG

Measure the side of the lea from the waist, over the hip, and straight down the leg to the



INSIDE LEG

Stand with your legs apart and measure the inside of one leg from the crotch to the ankle bone.

SHOULDER

Hold the end of the tape measure at the base of your neck (where a measure to the dent at To find this dent raise your arm slightly.



necklace would lie) and the end of your shoulder.



ankle bone.





NECK

Measure around the neck—snugly but not too tight—to determine collar size.



CROTCH DEPTH

Sit upright on a hard chair or stool and measure from the waist vertically down to the chair.



ARM

Bend your elbow and place your hand on your hip, then measure from the end of the shoulder over the elbow to the wrist bone.



Cutting out

Cutting out correctly can make or break your project. But first you need to examine the fabric in the store, looking for any flaws, such as a crooked pattern, and checking to see if the fabric has been cut properly from the roll—that is at a right angle to the selvage. If the fabric is creased, press it; if washable, wash it to avoid shrinkage later. After this preparation, you will be ready to lay the pattern pieces on the fabric, pin in place, and cut out.


Fabric grain and nap

It is important that the pattern pieces are cut on the correct grain, as this will make the fabric hang correctly and produce a longer-lasting item. The grain of the fabric is the direction in which the yarns or threads that make up the fabric lie. The majority of pattern pieces need to be placed with the straight of grain symbol running parallel to the warp yarn. Some fabrics have a nap due to the pile, which means the fabric shadows when it is smoothed in one direction. A fabric with a one-way design or uneven stripes is also described as being with nap. Fabrics with nap are generally cut out with the nap running down, whereas those without nap can be cut out at any angle.

GRAIN ON WOVEN FABRICS

The selvage is the woven, non-frayable edge that runs parallel to the warp grain.


Yarns that run the length of the fabric are called warp yarns. They are stronger than weft yarns and less likely to stretch.



Weft yarns run crossways, over and under the warp yarns.

The bias grain is diagonal—running at 45 degrees to the warp and weft. A garment cut on the bias will follow the contours of the body.

GRAIN ON KNITTED FABRICS



A knitted fabric also has a grain. Some knit fabrics stretch only one way while others stretch in both directions. Patterns for knit fabrics often need to be cut following the direction of the greatest stretch.

NAP DUE TO PILE

Fabrics such as velvet, corduroy, and velour will show a difference in color, depending on whether the nap is running up or down.

NAP IF ONE-WAY DESIGN



A one-way pattern—in this case flowers—that runs lengthwise in the fabric will be upside-down on one side when the fabric is folded back on itself.

NAP IF STRIPED




If the stripes match on both sides when the fabric is folded back, they are uneven and the fabric will need a nap layout.

Pattern preparation


Before cutting out, sort out all the pattern pieces that are required for the item you are making. Check them to see if any have special cutting instructions. Make pattern alterations, if necessary. If there are no alterations, just trim patterns to your size.



Using the pattern instruction sheet, which has drawings of the pattern pieces, select the pieces you require.



The instruction sheet also shows a suggested cutting-out layout for the item you are making, on different widths of fabric, with or without nap.



Trim multi-size pattern pieces:


according to the chosen size.

Single-size pattern pieces do not need to be cut to shape; just cut around them roughly if there is excess tissue.

Pattern layout


Fabric is usually folded selvage to selvage. With the fabric folded, the pattern is pinned on top, and both the right and left side pieces are cut at the same time. If pattern pieces have to be cut from single layer fabric, remember to cut matching pairs. For a fabric with a design, it is a good idea to have this on the outside so that you can arrange the pattern pieces to show off the design. If you have left and right side pattern pieces, they are cut on single fabric with the fabric right side up and the pattern pieces right side up.

PINNING THE PATTERN TO THE FABRIC




GENERAL GUIDE TO LAYOUT


Place the pattern pieces on the fabric with the printed side facing up. Some pieces will need to be placed to a fold.



If a piece has to be cut twice in a fold, this will need to be done after the other pieces have been cut and the fabric can be refolded. If using a single layer of fabric the pieces will need to be cut twice, reversing for the second piece.




LAYOUT FOR FABRICS WITH A NAP OR A ONE-WAY DESIGN




If your fabric needs to be cut out with a nap, all the pattern pieces need to be placed so the nap will run in the same direction in the made-up garment.

"Top" of fabric, from which direction the nap runs

LAYOUT ON A CROSSWISE FOLD



LAYOUT ON A CROSSWISE FOLD WITH A NAP



Occasionally a fabric is folded across the grain. This is usually done to accommodate very large pattern pieces.

If a crosswise fold is required in a fabric with a nap, fold the fabric with the wrong sides together, then cut into two pieces. Turn one around to make sure that the nap is running in the same direction on both pieces. Place the two pieces of fabric together, wrong side to wrong side.

LAYOUT ON A PARTIAL FOLD


The fabric is folded part way to enable you to cut some pattern pieces on a fold and the remainder from single fabric.



Stripes and plaid

For fabrics with a stripe or plaid pattern, a little more care is needed when laying out the pattern pieces. If the stripes and plaid are running across or down the length of the fabric when cutting out, they will run the same direction in the finished garment. So it is important to place the pattern pieces to ensure that the plaid and stripes match and that they run together at the seams. If possible, try to place the pattern pieces so each has a stripe down the center. With plaid, be aware of the hemline placement on the pattern.

EVEN OR UNEVEN STRIPES




Even stripes: When a corner of the fabric is folded back diagonally, the stripes will meet up at the fold.



Uneven stripes: When a corner of the fabric is folded back diagonally, the stripes will not match at the fold.

EVEN OR UNEVEN PLAID



Even plaid: When a corner is folded back diagonally, the plaid will be symmetrical on both of the fabric areas.



Uneven plaid: When a corner of the fabric is folded back diagonally, the plaid will be uneven lengthwise, widthwise, or both.

MATCHING STRIPES OR PLAID ON A SKIRT



Place one of the skirt pattern pieces on the fabric and pin in place.

Mark on the tissue the position of the boldest lines of the plaid or stripes.



Place the adjoining skirt pattern piece alongside, with notches matching and side seams even. Transfer the marks across.

Move the second pattern piece away, matching up the bold lines, and pin it in place.

MATCHING STRIPES OR PLAID AT THE SHOULDER



Mark the boldest lines of the stripes or plaid around the armhole on the front bodice pattern.




Place the sleeve pattern on to the armhole, matching the notches, and copy the marks on to the sleeve pattern.




Place the sleeve pattern on to the fabric, matching the marks to the corresponding bold lines, and pin in place.


LAYOUT FOR EVEN PLAID ON FOLDED FABRIC



LAYOUT FOR EVEN STRIPES ON FOLDED FABRIC



LAYOUT FOR UNEVEN PLAID OR STRIPES ON UNFOLDED FABRIC




Cutting out accurately

Careful, smooth cutting around the pattern pieces will ensure that they join together accurately. Always cut out on a smooth, flat surface such as a table—the floor is not ideal—and be sure your scissors are sharp. Use the full blade of the scissors on long, straight edges, sliding the blades along the fabric; use smaller cuts around curves. Do not nibble or snip at the fabric.

HOW TO CUT




MARKING DOTS




You can cut a small clip into the fabric to mark the dots: that indicate the top of the shoulder on a sleeve. Alternatively, these can be marked with tailor's tacks (see page 78).

MARKING NOTCHES



These symbols need to be marked on to the fabric as: they are matching points. One of the easiest ways to do this is to cut the mirror image of the notches out into the fabric. Rather than cutting out each notch separately, cut straight across from point to point.

CLIPPING LINES



A small clip or snip into the fabric is a useful way to mark: some of the lines that appear on a pattern, such as the center front line and foldlines.


Pattern marking

Once the pattern pieces have been cut out, you will need to mark the symbols shown on the tissue through to the fabric. There are various methods to do this. Tailor's tacks are good for circles and dots, or mark these with a water or air-soluble pen (when using a pen, it's a good idea to test it on a piece of scrap fabric first). For lines, you can use trace basting or a tracing wheel with dressmaker's carbon paper

TAILOR'S TACKS

As there are often dots of different sizes, it is a good idea to choose a different color thread for each dot size. It is then easy to match the colors as well as the dots. Have double thread in your needle, unknotted. Insert the needle through the dot from right to left, leaving a tail of thread. Be sure to go through the tissue and both layers of fabric.

Now stitch through the dot again, this time from top to bottom to make a loop. Cut through the loop, then snip off excess thread to leave a tail.



Carefully pull the pattern tissue away. On the top side, you will have four threads marking each dot. When you turn the fabric over, the dot positions will be marked with an X.




Gently turn back the two layers of fabric to separate them, then cut through the threads so that thread tails are left in both pieces of fabric.

TRACING PAPER AND WHEEL




This method is not suitable for all fabrics as the marks may not be able to be removed easily. Slide dressmaker's carbon paper against the wrong side of the fabric.

Run a tracing wheel along the pattern lines (a ruler will help you make straight lines).



Remove the carbon paper and carefully pull off the pattern tissue. You will have dotted lines marked on your fabric.

MARKERS




This method can only be used with a single layer of fabric.

Press the point of the pen into the center of the dot marked on the pattern piece.



Carefully remove the pattern. The pen marks will have gone through the tissue on to the fabric. Be sure not to press the fabric before the pen marks are removed or they may become permanent.

TRACE TACKING



This is a really useful technique to mark center front lines, foldlines, and placement lines. With double thread in your needle, stitch a row of loopy stitches, sewing along the line marked on the pattern.



Carefully pull away
the tissue. Cut through
the loops, then gently separate
the layers of fabric to show the
threads. Snip apart to leave
thread tails in both of the
fabric layers.




GATHERS, RUFFLES, TUCKS, DARTS, AND PLEATS

GATHERS

Gathers are an easy way to draw up a piece of larger fabric so that it will fit on to a smaller piece of fabric. The gather stitch is inserted after the major seams have been constructed, and it is best worked on the sewing machine using the longest stitch length that is available. On the majority of fabrics, two rows of gather stitches are required, but for very heavy fabrics, it is advisable to make three rows. Try to stitch the rows so that the stitches line up under one another.

Directory of gathers






How to make and fit gathers

Once all the main seams have been sewn, stitch the two rows of gathers so that the stitches are inside the seam allowance. This should avoid the need to remove them, because removing gathers after they have been pulled up can damage the fabric.



Sew one row of gathers at %in (1cm) and the second row at ½in (1.2cm). Leave long tails of thread for gathering. Break the sewn lines at the seams.







a mini iron, press the seam

very carefully to avoid creasing the gathers.

Secure the threads at the

one end to prevent



Even out the gathers


a 3-thread serger stitch.

and pin.




Ruffles

Ruffles can be single layer or double layer and are used to give a decorative gathered effect to a garment. The amount of fullness in a ruffle depends on the fabric used—to achieve a similar result, a fine, thin fabric will need twice the fullness of a thicker fabric.



Plain ruffle

A plain ruffle is normally made from a single layer of fabric cut on the straight of the grain. The length of the fabric needs to be at least two and a half times the length of the seam into which it is to be inserted or of the edge to which it is to be attached. The width of the ruffle depends on where it is to be used.





Place two rows of gather stitches along the raw edge—one row at ¾in (1cm) and the second row at ½in (1.2cm). Pull the threads to gather the fabric. The ruffle is now ready to be attached.

Double ruffle

- This is a useful ruffle on a fabric that is prone to fraying.
- Cut the fabric for the ruffle twice the required depth.
- Prold the fabric lengthwise, wrong side to wrong side.



- \nearrow Pin the raw edges together.
- Insert gathers along the raw edge.
- Pull up the gathers to fit.

Gathered ruffle

This type of ruffle can give a decorative effect on clothing and home goods.







After gathering, there will be gathers with a ruffle on one side of the stitch line and a short gathered heading on the other. Pull out the basting stitches.

Sewing a ruffle to an edge

If a ruffle is not in a seam, then it will be attached to an edge. The edge of the seam will require neatening, which is often best done by using a binding method as it is more discreet. A self-bound edge, where the seam is wrapped on to itself, is suitable for fine, delicate fabrics. For thicker fabrics, use a bias binding to finish the edge.

seam allowance.

SELF-BOUND FINISH



Place the gathered ruffle to the edge of the fabric, right side to right side. Pin in place.



Wrap the longer, fabric side of the seam over the gathered seam, tucking under the raw edge. Pin in place.



to half

 \sum Sew the wrapped seam to secure. Make sure it is attached to the seam only.

BIAS-BOUND FINISH

Sew the gathered ruffle to the edge of the fabric, right side to right side, using a 5/4 in (1.5cm) seam allowance (see steps 1 and 2, opposite).





Sewing around a corner

It can be difficult to sew a ruffle to a corner and achieve a sharp point. It is easier to fit the gathers into a tight curve, which can be done as the ruffle is being applied to the corner.



to fit along one side

of the fabric seam and

pin in place.

Pit the gathers into a tight curve at the corner.



Sew the ruffle in place.



right side. The corner


will have a tight curve.

and sew in place.

Layer the seam.

Sewing a ruffle

Once the ruffle has been constructed it can either be inserted into a seam or attached to the edge of the fabric (see page 86). The two techniques below apply to both single and double ruffles.



Shirring

Shirring is the name given to multiple rows of gathers. It is an excellent way to give fullness in a garment. If made using shirring elastic in the bobbin, shirring gathers can stretch. On heavier fabrics, such as for home goods, static shirring is more suitable.

MACHINE SHIRRING



 $\label{eq:set-set-set-set} 3 \text{ Set the machine to a stitch} \\ \text{length of 5.0.}$

Sew a row of machining across the fabric.



Sew a second row of machining, 5% in (1.5cm) from seam. Make sure the rows of sewing are parallel.

WAFFLE SHIRRING

For this, two rows of shirring cross each other at right angles. Sew horizontal rows of shirring using shirring elastic in the bobbin (see above)......





Cross these with vertical rows of shirring.

Tucks

A tuck is a decorative addition to any piece of fabric, and can be big and bold or very delicate. Tucks are made by sewing evenly spaced folds into the fabric on the right side, normally on the straight grain of the fabric. As the tucks take up additional fabric, it is advisable to make them prior to cutting out.

Directory of tucks




Plain tucks


A plain tuck is made by marking and creasing the fabric at regular intervals. A row of machine stitches are then worked adjacent to the fold.



Make sure the lines are parallel.



straight, and press in place.





Other simple tucks

These tucks are also made by marking and creasing the fabric. The positioning of the sewn line determines the type of tuck.

SPACED TUCKS



These are similar to a plain tuck, but with wider regular spacing. Press the tucks in place along the foldlines and pin. Sew ¾in (1cm) from the foldline. Press all the tucks in one direction.

PIN TUCKS



These narrow, regularly spaced tucks are stitched very close to the foldline, which may require moving the machine needle closer to the fold. Use the pintuck foot on the sewing machine.

TWIN NEEDLE TUCKS



For these regularly spaced tucks, use the twin needle on the sewing machine. The twin needle produces a shallow tuck that looks very effective when multiple rows are stitched.

BLIND TUCKS



These are stitched so that they touch. Fold back all but one tuck and sew it in place. Continue sewing the tucks in this way so that the folded edge of each covers the line of the previous tuck.

Darted tucks

A tuck that stops to release the fullness is known as a darted tuck. It can be used to give fullness at the bust or hip. The shaped darted tuck is sewn at an angle to release less fabric, while the plain darted tuck is sewn straight on the grainline.

SHAPED DARTED TUCKS

Transfer any pattern markings to the fabric.



Fold the fabric right side to right side. On the wrong side of the fabric, sew at an angle to the folded edge.

PLAIN DARTED TUCKS



→ Make in the same way as I a shaped darted tuck (see left), but sew parallel to the folded edge.



The tuck as seen from the right side.


Cross tucks

These are tucks that cross over each other by being sewn in opposite directions.


Secure the stitches.

Stop at the point indicated

on your pattern.



first: fold the fabric wrong side to wrong side along the crease lines. Sew 3/16in (5mm) from the folded edge.




tucks in the same way. same direction.


Shell tucks

A shell tuck is very decorative as it has a scalloped edge. Shell tucks can be easily sewn using the sewing machine.

On heavy fabric and delicate fabrics, it may be preferable to make the tucks by hand.

MACHINE SHELL TUCKS






Use the embroidery foot on the sewing machine and set the sewing machine to a shell hem stitch.


Sew along the fold, keeping the fold close to the inside opening of the machine foot.



The finished tucks should be stitched at regular intervals.

SHELL TUCKS BY HAND






Bevery $\frac{1}{2}$ in (1.25cm), make an over-stitch through the fold to produce a scallop.

Darts


A dart is used to give shape to a piece of fabric so that it can fit around the contours of the body. Some darts are sewn using straight sewn lines and other darts are stitched using a slightly curved line. Always sew a dart from the point to the wide end because you are able to sink the machine needle into the point accurately and securely.

Directory of darts





Plain dart

This is the most common type of dart and is used to give shaping to the bust in the bodice. It is also found at the waist in skirts and pants to give shape from the waist to the hip.



Tailor tack the points of the dart as marked on the pattern, making one tack at the point and two to mark the wide ends.






Pin through the tailor's tacks to match them.




Baste along the dart line, joining the tailor's tacks. Remove the pins.




Machine sew alongside the basting line. Remove the bastes.



Sew the machine threads back into:
the line of the dart to secure them.




Press the dart to one side: (see page 97).




The finished dart on the right side.

Contour or double-pointed dart

This type of dart is like two darts joined together at the fat end. It is used to give shape at the waist of a garment. It will contour the fabric from the bust into the waist and then out again for the hip.










French dart

A French dart is used on the front of a garment only. It is a curved dart that extends from the side seam at the waist to the bust point. As this is a long dart that is shaped, it will need to be slashed prior to construction, in order for it to fit together and then lie flat when pressed.



Pressing a dart

If a dart is pressed incorrectly, this can spoil the look of a garment. For successful pressing, you will need a tailor's ham and a steam iron on a steam setting. A pressing cloth may be required for delicate fabrics such as silk, satin, and chiffon, and for lining fabrics.






Move the iron from the point toward the wide end of the dart to press the dart flat, open, or to one side, depending on the type of dart.

Pleats

A pleat is a fold or series of folds in fabric. Pleats are most commonly found in skirts where the pleats are made to fit around the waist and hip and then left to fall in crisply pressed folds, giving fullness at the hemline. It is important that pleats are made accurately, otherwise they will not fit the body and will look uneven. Foldlines and placement lines, or foldlines and crease lines, are marked on the fabric from the pattern. It is by using a combination of these lines and the spaces between them that the pleats are made.



Pleats on the right side


Knife pleats are normally formed on the right side of fabric. They can all face the same direction or may face opposite directions from opposite sides of the garment. Knife pleats have foldlines and placement lines.

Mark the placement lines and foldlines with trace tacks. Use one color thread, such as red, for placement lines.....

Use a contrasting color thread, such as blue, to mark foldlines.....

Cut through the thread

loops and remove the pattern pieces carefully.



Fold the fabric along the foldline, creasing accurately along the trace tacks.

Bring the creased line on to the placement line. Pin to secure.




With the right side of the fabric uppermost, cover with a silk organza pressing cloth.

Using a steam iron on a steam setting, press the pleats in place. Keep the iron still as opposed to moving it around, and eject a shot of steam each time you lift it to a new position. Repeat this action across all of the pleats.



Baste along the foldlines about 1/16in (2mm) from the folded edge, through all the layers.

Remove the pins and the trace basting on this part of the pleat.




Turn the fabric to the wrong side and insert thin strips of construction paper under the pleat fabric.

Press again with the steam iron and a silk organza cloth. The paper will prevent the fabric from leaving an imprint on the right side.


Pleats on the wrong side

Some pleats, including box (shown below) and inverted pleats, are formed on the wrong side of the fabric. As the pleats are made on the wrong side, you can mark the crease lines and foldlines with a tracing wheel and dressmaker's carbon paper. Use a ruler to guide the tracing wheel, because these pleats need to be straight lines.

Mark the crease lines and foldlines on the wrong side of the fabric, using different colors for the different lines. The lines must be marked down the full length of the fabric.




Also mark the stop line that shows: where to stop stitching. Remove the pattern pieces.




Flatten the pleat on the wrong side so that the foldline is lying on top of the machine stitches. Make sure that the fabric on either side of this foldline to the crease line is equal on both sides.

 $\label{eq:bounds} B^{\text{pring}} \text{ the two crease lines that are } \\ either side of the foldline together \\ \text{and pin in place}.$



Be sure the foldline is along the fold: in the fabric.





Press each section of the pleat in turn, lifting the iron rather than moving it on the fabric.

 $\label{eq:basic_basic} Baste through the two layers of fabric where the crease lines have been pinned together, along the entire length of the pleat.$





If the fabric is in danger of being: marked on the right side with the pleats, place some strips of construction paper under the pleats on the wrong side, then press again on the wrong side.

Top-stitching and edge-stitching pleats

If a pleat is top-stitched or edge-stitched, it will hang correctly and always look crisp. It will also help the pleats on the skirt to stay in shape when you are sitting.

TOP-STITCHING KNIFE PLEATS

Once the knife pleats have been pressed and all bastes and markings removed, place some pins across the pleat to stop it from moving.

Machine sew from the right


Once the knife pleats have been pressed and all bastes and markings removed, place some pins across the pleat to stop it from moving.

of the pleat and

sew to the waist.

TOP-STITCHING BOX PLEATS THAT HAVE A SQUARE END

This requires sewing down on either side of the foldline. Sew down one side about $^3\!/_{16}$ in (5mm) from the foldline.




Pivot and sew horizontally across the end of the pleat stitches.

Pivot again and sew up the other side of the foldline about 3/iein (5mm) from the foldline.

TOP-STITCHING BOX PLEATS THAT HAVE A POINTED END

Sew down one side 3/16in (5mm) from the foldline, then pivot and sew diagonally to the center.



Pivot again and sew diagonally the other side and back to the waist % 16 in (5mm) from the foldline.


EDGE-STITCHING KNIFE PLEATS

side approximately

1/16in (2mm) from


the fold.

After pressing the pleats into shape, stitch ½ (2mm) from the fold.



EDGE-STITCHING AND TOP-STITCHING PLEATS

Edge-stitch first the edge of the pleat about 1/16in (2mm) from the folded edge.



Top-stitch through all the layers, continuing at 1/16in (2mm) from the fold, to the waist.

TOP-STITCHING KICK PLEATS OR INVERTED PLEATS

This pleat is pressed to the right. Just below the sewn line that makes the pleat, sew a line diagonally, to secure the pleat fabric at the back.




Pull the ends of the machine stitching through to the reverse.

Pleats on curtains

Pleats are used in home goods, particularly at the top of curtains, to reduce the fabric so that the curtain will fit on to its track and fit the window. The easiest way to pleat the upper edge of a curtain is to apply a curtain tape. Tapes are available in various depths and will pull the curtain into pencil pleats or goblet pleats. The most common tape used for pencil pleating is $3\frac{1}{4}$ in (8cm) deep. A curtain is normally cut two and a half to three times the width of the window. The curtain tape will reduce the fabric by this much as it pleats up.

PREPARING THE CURTAIN TO TAKE THE TAPE


Turn under the two side edges of the curtain by using a double hem of 1 in (2.5cm), i.e. turn the fabric 1 in (2.5cm) once and then the same again.



Turn the top of the curtain down by 1 in (2.5cm) and pin.

Side edge






Reduce the bulk at the top edge on the comers and by trimming away the side hem.

Baste the upper edge into place. To ensure the corners are square, pivot and realign the edge of the fabric with the marks on the bobbin cover.

MAKING A POCKET FOR THE STRINGS



A small pocket needs to be made to take the strings that are used to pull up the tape. Cut a rectangle of spare fabric 6 x 3½in (15 x 8cm).

2 Turn one short edge wrong side to wrong side and sew to make a single hem.

Pold the rectangle right side to right side with a ¾in (2cm) seam at the upper edge free.


A Sew down the sides and clip the corners.



Turn through to the right side and press.

then sew.

PENCIL PLEATS



Take the curtain tape and release the strings at the one end, making sure they are all visible on the same side.


Place the top of the tape 3/16in (5mm) down from the folded edge of the curtain. Pin in place, stretching the tape as you do so. Turn under the short end, avoiding the strings and pin.



 $\label{eq:sew_the_sew} Sew \text{ the upper edge of the tape to the} \\ \text{curtain fabric. Make sure the strings} \\ \text{stay free.}$




Before sewing the lower edge of the tape, place the pocket you made under the end of the tape.





end with the pocket to make the pleats.





At the opposite end of the tape, sew across each string individually to prevent it from being pulled out.



Turn the curtain over to check that the pencil pleats are evenly spaced and will fit the window. Adjust if necessary.

GOBLET PLEATS

Goblet pleats are three pleats together at regular intervals. When the tape is pulled up, the pleats are close together at the base and fan out at the top. Prepare the curtain to take the tape and make the pocket (see opposite page).



2 Attach the tape in the same way as for pencil pleats (left).

 $\label{eq:afterpulling} After pulling up the tape, secure it by hand on the right side at the base of the tape.$



Hand sew the upper edge of the: pleats at the back.




HEMS AND EDGES

Hems and edges

The edge of a piece of fabric can be finished with a hem—which is normally used on garments—or with a decorative edge, which is used for crafts and home goods as well as garments. Sometimes the style of what is being constructed dictates the finish that is used, and sometimes it is the fabric.

Directory of hems



Marking a hemline

On a garment such as a skirt or a dress, it is important that the hemline is level all around. Even if the fabric has been cut straight, some styles of skirt—such as A-line or circular—will "drop," which means that the hem edge is longer in some places. This is due to the fabric stretching where it is not on the straight of the grain. Poor posture will also cause a hem to hang unevenly.

You'll need a helper for this method. Put on the skirt or dress (without shoes). With the end of the ruler on the floor, measure straight up on to the skirt.

USING A RULER



106

Turning up a straight hem

Once the crease line for the hem has been marked by the pins, you need to trim the hem allowance to a reasonable amount. Most straight hems are about 1½in (4cm) deep.

Gently press the crease line of the hem with the iron.

Don't press too hard as you do not want a sharp crease.



Trim the seam allowance back to reduce the bulk. If wished, neaten the raw edge.

Turn up the hem at the crease.



Baste the hem into position close to the crease line. The hem is now ready to be sewn in place by hand or machine.

Hand-sewn hems


One of the most popular ways to secure a hem edge is by hand. Hand sewing is discreet and, if a fine hand sewing needle is used, the stitches should not show on the right side of the work.

TIPS FOR SEWING HEMS BY HAND

- 1 Always use a single thread in the needle—a polyester all-purpose thread is ideal for hemming.
- **2** Once the raw edge of the hem allowance has been neatened by one of the methods below, secure it using a slip hem stitch. For this, take half of the stitch into the neatened edge and the other half into the wrong side of the garment fabric.
- **3** Start and finish the hand sewing with a double stitch, not a knot, because knots will catch and pull the hem down.
- **4** It is a good idea to take a small back stitch every 4in (10cm) or so to make sure that if the hem does come loose in one place, it will not all unravel.


CLEAN FINISH

This is suitable for fine and lightweight fabrics. Turn the raw edge of the hem allowance to itself, wrong side to wrong side. Baste the edge and then sew.



Z Lightly press the hem.....

Baste the hem A Roll the edge sewn back and sew underneath it.




Using a small slip hem stitch, secure

The edge of the hem to the wrong side of the fabric. Roll the edge back into place.

Remove the basting and press lightly.

BIAS-BOUND FINISH

This is a good finish for fabrics that fray or that are bulky. Turn up the hem on to the wrong side of the garment and baste close to the crease line.



Pin the bias binding:
to the raw edge of the hem allowance.

 $\label{eq:continuous} \begin{tabular}{ll} \b$


Turn down the bias over the raw edge and press.



Using a slip hem stitch, join the edge of the bias to the wrong side of the fabric. Remove the basting and press lightly.


ZIGZAG FINISH

I Use this to neaten the edge of the hem on fabrics that do not fray too badly. Set the sewing machine to a zigzag stitch, width 4.0 and length 3.0. Sew along the raw edge. Trim the fabric edge back to the zigzag stitch.



Turn the hem on to the wrong side of the garment and: baste in place close to the crease line.


Fold back the zigzag-stitched edge. Using a slip hem stitch, sew the hem into place.



Roll the edge back into position. Remove the basting and lightly press.


PINKED FINISH

Pinking shears can give an excellent hem finish on difficult fabrics. Sew a row of straight stitches along the raw edge, %in (1cm) from the edge. Pink the raw edge.



2 Turn up the hem to the wrong side of the garment and baste \vdots in place close to the crease line.

Fold back the edge along the sewn line and hand sew the hem in place with a slip hem stitch.....




Roll the hem edge back into place. Remove the basting and lightly press.

108

Hems and edges

Turning up a curved hem


When the hem on a shaped skirt is turned up, it will be fuller at the upper edge. This fullness will need to be eased out before the hem is sewn.




Mark the hemline, placing the pins vertically to avoid: squashing the fullness out of the upper raw edge.



Baste the hem into position close to the crease line.



Make a row of long machine stitches, length 5.0, close to the raw upper edge of the turned-up hem.




Pull on one of the threads of the long stitches to tighten the fabric and ease out the fullness.

Use the steam iron to shrink out the remainder of the fullness.

The hem is now ready to be sewn in place by hand or machine.

CURVED HEM FINISH

With a curved hem on a cotton or firm fabric, it is important that any fullness does not bulge on to the right side. Prior to turning up the hem into position, zigzag the raw edge, using stitch width 4.0 and stitch length 3.0.



Sew a row of straight stitches 1/8 in (3mm) below the row of zigzag stitching, using stitch length 5.0.

Pin the hem into position, placing the pins vertically.

Baste the hem into position close to the crease line.

5 Pull on the straight stitching to tighten the fabric.



Roll the zigzagged edge back to the straight stitched line: and hand sew the hem in place using a slip hem stitch.

Remove the basting and press lightly.


Machine-sewn hems

On many occasions, the hem or edge of a garment or other item is turned up and secured using the sewing machine. It can be sewn with a straight stitch, a zigzag stitch, or a blind hem stitch. Hems can also be made on the serger.

SINGLE TURN HEM




DOUBLE TURN HEM




110 Hems and edges

BLIND HEM STITCH



Hems on difficult fabrics


Some very fine fabrics or fabrics that fray badly require more thought when a hem is to be made. This technique works very well on delicate fabrics.



Rolled hems

A rolled hem is used on lightweight fabrics. It is often found on home goods as well as garments. To make it, the fabric is rolled to the wrong side by using the rolled hem foot on the sewing machine.

STRAIGHT-STITCHED ROLLED HEM



Use the rolled hem foot on the sewing: machine and a straight stitch.


ZIGZAG-STITCHED ROLLED HEM



Use the rolled hem foot on the sewing: machine and a zigzag stitch.

Fused hem


A fused hem is useful for a fabric that is difficult to hand sew, as well as for an emergency hem repair. It uses a fusible web that has a fusible adhesive on both sides.



with with a serger or zigzag stitch.

Insert the fusible hemming tape

between the hem and the wrong side of the garment. Make sure the tape sits just below the serger or zigzag stitch. Pin the tape in place.



Cover the hem allowance with a pressing cloth and, using a steam iron, press the edge of the hem to fuse the tape to the fabric. Once cool the hem will be stuck in place. Remove the basting stitches and pins.


hem in place close to


the crease line.

Bias-bound hems


A bias-bound hem will give a narrow decorative edge to a garment or an item of home furnishing. It is particularly useful for curved shapes, to finish them neatly and securely. On a chunky or bulky fabric, a double bias is used so that it will be more substantial and hold its shape better. A double bias is also used on sheer fabrics as there will be no visible raw edges. The bias strip can be made from purchased bias binding or cut from a matching or contrasting fabric.

SINGLE BIAS-BOUND HEM






DOUBLE BIAS-BOUND HEM



Attaching a lace trim

A lace edge can give a look of luxury to any garment. There are many ways of applying lace, depending on how the lace has been made. A heavy lace trim has a definite edge to be sewn on to the fabric. Lace edging has a decorative edge and an unfinished edge, whereas a galloon lace has decorative scallops on both edges.

LACE EDGING













Place the entire piece of lace to the: I right side of the fabric. Align the edge of the lace with the raw edge of the fabric. Pin in place.



Wrong side

edge of the lace, following the shape following the shape. of the stitches.



HEAVY LACE TRIM



- Pin the lace to the right side of the fabric.
- Using a small zigzag stitch, sew along the edge of the lace. All of the stitches should be on the lace.
- Trim away surplus fabric behind.

Applying a flat trim

On some items a flat trim braid or ribbon is added for a decorative effect. This may be right on the hem or edge, or placed just above it. To achieve a neat finish, any corners should be mitered.



Pin the trim to the fabric, wrong side of the trim to right side of the fabric.

At the corner point where the trim is to be mitered, fold the trim back on itself and secure with a pin.



Sew across the trim at 45 degrees from the edge of the fold, through all layers.

Remove excess trim




5 Open the trim out and press.

Sew the inner and outer sides of the trim to the fabric, close to the edge. Be sure the stitches at the corners are sharp.

Piped edges

A piped edge can look very effective on a garment, especially if it is made in a contrasting color or fabric. Piping is also an excellent way of finishing special-occasion wear as well as home goods. The piping may be single, double, or gathered.

SINGLE PIPING




DOUBLE PIPING

Different thicknesses of piping cord can be used for this. Make up single piping (see steps 1–3, page 115).

color if you like.

Cut another bias strip, in a contrasting



Place a second piping cord to the wrong side of the contrast strip.



Wrap the contrast strip around the cord and sew.




Attach to the edge of the work as for single piping (see steps 4–7, page 115). On the right side, there is a double row of piping at the edge.

GATHERED PIPING

This is a great technique to try on cushions. Cut a bias strip 2in (5cm) wide. Sew the bias strip loosely around a piece of piping cord. Secure the cord to the bias at one end.



Push the bias along the cord to gather.




Attach to the edge of the work as for single piping (see steps 4–7, page 115).

Applying other trims

There are many kinds of trims—ribbons, braids, beads, feathers, sequins, fringes, and so on—that can be applied to a fabric edge. If a trim is made on a narrow ribbon or braid it can often be inserted into a seam during construction. Other trims are attached after the garment or item has been completed.

INSERTING A TRIM IN A SEAM

Place the trim to the right side of one piece of fabric, with the beaded or other decorative edge pointing away from the raw edge. The edge of the trim should be on the 5%in (1.5cm) sewn line. Baste in place.



Sew along the trim using the zipper foot.



Place the other piece of fabric to: the first one, right side to right side. Sew again to join them.



Turn to the right side. Press carefully.

The trim should hang free.

ATTACHING A TRIM TO AN EDGE



Pin the trim in position along the finished edge of the work. Be sure the trim is aligned to the edge. Baste in place.



Using the zipper foot, sew in place close to the upper edge, leaving the lower edge of the trim free.

HAND STITCHING A TRIM



Delicate trims are best hand sewn in place because machine sewing the trim may damage it. Place the trim in position and carefully sew down with a flat fell stitch.




FASTENERS

BUTTONS

Buttons are one of the oldest forms of fastening. They come in many shapes and sizes, and can be made from a variety of materials including shell, bone, plastic, nylon, and metal. Buttons are sewn to the fabric either through holes on their face, or through a hole in a stalk called a shank, which is on the back. Buttons are normally sewn on by hand, although a two-hole button can be sewn on by machine.


Directory of buttons



Sewing on a 2-hole button

This is the most popular type of button and requires a thread shank to be made when sewing in place. A toothpick will help you to sew on this type of button.

- Position the button on the fabric. Start with a double stitch and double thread in the needle......
- Remove the toothpick.
- \int Take the thread through to the back of the fabric.



Place the toothpick on top of the button. Sew up and down through the holes, going over the stick.



Wrap the thread around the thread loops under the button to make a shank.





Buttonhole stitch over the loop of threads on the back of the work.

Sewing on a 4-hole button

This is stitched in the same way as for a two-hole button except that the threads make an X over the button on the front.

Position the button on the fabric.
Place a toothpick on the button.





Using double thread, sew up and idea down through alternate sets of holes, over the toothpick. Make an X shape as you stitch.



Wrap the thread around the thread loops under the button to make the shank.



On the reverse of the fabric, buttonhole sew over the thread loops in an X shape.

Sewing on a shanked button

When sewing this type of button in place, use a toothpick under the button to enable you to make a thread shank on the underside of the fabric.

Position the button on the fabric. Hold a toothpick on the other side of the fabric, behind the button.



Using double thread, sew the button to the fabric, through the shank.



Be sure each stitch goes through the fabric and around the toothpick beneath.



Remove the toothpick. Work buttonhole stitch over the looped thread shank.

Sewing on a reinforced button

A large, heavy button often features a second button sewn to it on the wrong side and sewn on with the same threads that secure the larger button. The smaller button helps support the weight of the larger button.



Position the large button on the right side of the fabric. Hold a smaller button beneath the fabric, in line with the large button.

Sew on the large button, sewing through to secure both buttons together.



When the sewing is complete, wrap the thread around the thread loops beneath the larger button. Secure with a double stitch.

Covered buttons

Covered buttons are often found on expensive clothes and will add a professional finish to any jacket or other garment you make. A purchased button-making gadget will enable you to create covered buttons very easily.



Cut out the button pattern from interfaced fabric.


Sew a gather thread around the edge.

Place the button top on the interfaced

side of the fabric



 $\dot{\mathbf{5}}$ Pull up the gathers and secure with a double stitch around the shank of the button top.



Put the button in the correct hole in the button-maker.
Push well in.



 $\frac{\cdot}{7}$ Place the button back on top of the button.



Take the other side of the button-maker and press down on the button back until it clicks into position.



Remove the button from the button-maker and check to be sure the back is firmly in place.




The finished covered button.


buttonholes

A buttonhole is essential if a button is to be truly functional, although for many oversized buttons, a snap fastener on the reverse is a better option, because the buttonhole would be just too big and could cause the garment to stretch.


Directory of buttonholes and button loops



BASIC BUTTONHOLE




ROUND-END BUTTONHOLE




KEYHOLE BUTTONHOLE



BOUND BUTTONHOLE





BUTTON LOOPS

SPACED BUTTON LOOPS

Stages of a buttonhole

A sewing machine stitches a buttonhole in three stages. The stitch can be slightly varied in width and length to suit the garment or craft item, but it needs to be tight and close together.



Sew the first side of the buttonhole.



Sew a bar baste at one end.



Sew the second side and bar baste at

Positioning buttonholes

Whether the buttonholes are to be stitched by machine or another type of buttonhole is to be made, the size of the button will need to be established in order to work out the position of the button on the fabric.

Place the button on a sewing gauge and use the slider to measure the button's diameter.....



On the right-hand side of the fabric, as the garment will be worn, work a row of basting stitches along the center front line.



) Work a second row of bastes the diameter of the button away.

Position the buttons between the t baste lines. Sew lines at right angles where the buttonholes are to be placed.

Vertical or horizontal?

As a general rule, buttonholes are only vertical on a garment when there is a placket or a strip into which the buttonhole fits. All other buttonholes should be horizontal. Any strain on the buttonhole will then pull to the end and prevent the button from coming undone.

HORIZONTAL BUTTONHOLES



These are positioned with the end on the basted center line:

VERTICAL BUTTONHOLES



These are positioned with the buttonhole centered on the basted: center line.

Machine-made buttonholes


Modern sewing machines can sew various types of buttonhole, suitable for all kinds of garments. On many machines the button fits into a special foot, and a sensor on the machine determines the correct size of buttonhole. The width and length of the stitch can be altered to suit the fabric. Once the buttonhole has been stitched, always cut through with a buttonhole cutter, to ensure that the cut is clean.

BASIC BUTTONHOLE




The most popular shape for a buttonhole is square on both ends.

ROUND-END BUTTONHOLE



A buttonhole featuring one rounded end and one square end is used on lightweight jackets.

KEYHOLE BUTTONHOLE




This is also called a tailor's buttonhole. It has a square end and a keyhole end, and is used on jackets and coats.

In-seam buttonhole

This is a buttonhole formed in a seam allowance. It is found down decorative center fronts that feature seam detailing. It is a very discreet buttonhole.



Reinforce the seam with a fusible tape on one side



Baste the opening closed.



Press the seam open. The bastes will show.



to form the buttonhole.

BUTTON LOOPS

A buttonhole is not the only way of using buttons. Buttons can also be fastened by means of a fabric loop, which is usually attached at the edge of a garment. Fabric loops are often found on the back of special-occasion wear, where multiple loops secure rows of small, often covered buttons.

Fabric button loop

This button loop is formed from a bias strip. Choose a smooth fabric for the strip as it will be easier to turn through.

A fabric loop is used with a round ball-type button.

Cut a bias strip 1½in (4cm) wide. Fold lengthwise, right side to right side, and pin together.


 $\sum \text{Sew with a seam allowance of } \frac{1.5\text{cm}}{\text{min}} \text{ (1.5cm) along the strip,}$ keeping the edge of the machine foot against the folded edge.





stitches. This is for strength.





Turn the bias strip to the right side, using a loop turner.:


Pin the prepared loop strip to the ironing board and press with a steam iron.

Spacing the loops

Once the loops have been made, the next step is to attach them to the garment. It is important that all the loops are the same size and positioned the same distance apart. To achieve this you will need to baste your fabric to mark the placement lines. The loops go on the right-hand front or the left-hand back of the work.



Mark the placement lines on the fabric using basting stitches. Be sure the horizontal lines are equally spaced.




Pin the loops to the fabric.
The folded end of the loop should be on the inner basting line and the cut ends to the raw edge. Center the loop over the baste line.

3 Sew the loops just inside the seam allowance at the center line.



Sew another row to : ensure the loops are secure.

Place the facing or lining over the loops to finish.



The completed loop: will extend from the edge of the fabric.

Corded loop

It is possible to make a very fine button loop that has a cord running through it. This type of loop is suitable for lightweight fabrics. Use a shanked button with a corded loop.

Cut a bias strip 1½in (4cm) wide, and any length. Cut a piece of cord twice the length of the strip.



Wrap the cord in the bias strip, folded wrong side to wrong side.

Pin. Make sure the bias strip is near to one end of the cord.

Sew along the bias strip.

next to, but not too close to, the cord.

Sew another row the first stitches.

Trim away the bias strip: Sew through the cord and

Trim away the bias strip:

Close to the stitches.

Sew through the cord and:

bias strip in the center of the cord

and near the end of the bias strip.


At the center point, ease the fabric over the cord to turn it to
the right side.

Trim off the exposed ends of cord from the fabric loop.



OTHER FASTENINGS

There are many alternative ways to fasten garments, craft projects, and other items, some of which can be used instead of or in conjunction with other fasteners. These include hooks and eyes, snaps, and tape fasteners.



Snaps

A snap is a ball and socket fastener that is used to hold two overlapping edges closed. The ball side goes on top and the socket side underneath. Snaps can be round or square and can be made from metal or plastic.

Baste the ball and socket halves of the snap in place.....

Secure permanently using a buttonhole stitch through each hole in the outer edge of the snap half.

Remove the bastes.







PLASTIC SNAPS


A plastic snap may be white or clear plastic and is usually square in shape. Sew in place as for a metal snap (see above).



Hooks and eyes

There are a multitude of different types of hook and eye fasteners. Purchased hooks and eyes are made from metal and are normally silver or black in color. Different shaped hooks and eyes are used on different garments—large, broad hooks and eyes can be decorative and sewn to show on the outside, while the tiny fasteners are meant to be discreet. A hook that goes into a hand-worked eye produces a neat, close fastening.

ATTACHING HOOKS AND EYES



Secure the hook and eye in place with a basting stitch. Make sure they are in line with each other.



Sew around each circular end with a buttonhole stitch.



Place a few over-stitches under the hook to stop it from moving.

HAND-WORKED EYE



Using a double thread, work several: small loops into the edge of the fabric.



2 Buttonhole stitch over these loops.



The completed loop will have a neat row of tight buttonhole stitches.

PANT HOOK AND EYE



The hook and eye fastener for pant and skirt waistbands is large and flat. Baste the hook and eye in position. Do not baste through the holes that are used for securing.



Buttonhole stitch through each hole on the hook and eye. Be careful not to sew through the fabric, as you don't want stitches to show through on the outside of the garment.

Tape fasteners

In addition to individual small fasteners, there are fasteners in the form of tapes that can be sewn or stuck on. VelcroTM, a hook and loop tape, is available in many colors and types. Sewn-on VelcroTM is ideal for both clothing and soft furnishings, while the stick-on variety can be used to fix curtain valances and blinds to battens on windows. Plain cotton tape with snap fasteners is used primarily in home goods. Hook and eye tape is found in underwear or down the front of a shirt or jacket, where it can be very decorative.

VELCROTM



Pin the Velcro[™] in place. The loop side should be underneath and the hook side on top.



Sew around all the edges.

Grommets

A grommet fastening can be decorative and is often found on bridal wear and prom dresses. A piece of boning needs to be inserted into the fabric between the edge and the grommets, to give strength. You will require grommet pliers to punch the holes and then insert the grommets.

Using the pliers, punch out the holes for the grommets at 1½-1½in (3-4cm) intervals.



Place a grommet in each hole. Change the heads on the pliers and squeeze the grommet in place.




To close, lace ribbon across from grommet to grommet: and finish with a bow.

132

Zippers

The zipper is probably the most used of all fastenings. There are a great many types available, in a variety of lengths, colors, and materials, but they all fall into one of five categories: skirt or pant zippers, metal or jeans zippers, invisible zippers, open-ended zippers, and decorative zippers.

Directory of zippers



How to shorten a zipper

Zippers do not always come in the length that you need, but it is easy to shorten them. Skirt or pant zippers and invisible zippers are all shortened by sewing across the teeth or coils, whereas an open-ended zipper is shortened at the top and not at the bottom.

SHORTENING A SKIRT/PANT OR INVISIBLE ZIPPER




SHORTENING AN OPEN-ENDED ZIPPER



Marking for placing zippers


For a zipper to sit accurately in the seam, the seam allowances where the zipper will be inserted need to be marked. The upper seam allowance at the top of the zipper also needs marking to ensure that the zipper pull sits just fractionally below the sewn line.





Lapped zipper

A skirt zipper in a skirt or a dress is usually put in by means of a lapped technique or a centered zipper technique (see page 137). For both of these techniques, you will require the zipper foot on the sewing machine. A lapped zipper features one side of the seam—the left-hand side—covering the teeth of the zipper to conceal them.





Using the zipper foot, sew along the baste line to secure the zipper tape to the fabric. Sew from the bottom of the zipper to the top.



Fold back the left-hand seam allowance by %in (1.5cm) and press. Place the folded edge over the sewn line of the other side. Pin and then hand baste along foldline.



Open-ended zipper

The open-ended zipper is used on garments where the two halves need to be fully opened in order to put the garment on—for example, on a jacket or cardigan.

On both pieces of fabric, turn under the seam allowance at the center front and baste. Neaten by preferred method.

 $\label{eq:continuous} 3^{\text{Place}} \text{ the folded edge of the center} \\ \text{front about $\frac{1}{2}$ in (3mm) from the} \\ \text{zipper teeth to allow for the pull to move} \\ \text{up and down. Pin in place.}$

Using the zipper foot, sew the zipper in place. Start with the zipper open. Sew 2in (5cm), then place the needle in the work, raise the zipper foot, and close the zipper.



Turn up the hem allowance and:



Place the bottom of the zipper at the hem edge.



Sew to the end of the zipper tape and secure.

 $\begin{tabular}{ll} \begin{tabular}{ll} \beg$



Of the zipper and, using the zipper foot, sew in place as you did on the first side.



Once the zipper is sewn in place, check that the hems line up. If they do not, you will have to rip the seam and start again.



The zipper should open completely.

Centered zipper

With a centered zipper, the two folded edges of the seam allowances meet over the center of the teeth, to conceal the zipper completely.

Sew the seam, leaving a gap for the zipper.



Baste the rest of the seam allowance.

3 Press the seam open lightly.

On the wrong side, lift the seam allowance and the zipper tape away from the main fabric. Pin.



Yorking from the right side of the work, sew down one side, across the bottom, and up the other side of the zipper.

Remove the tacks and press.

The finished zipper from the right side.




Center the zipper behind the tacked part of the seam.

Pin and then baste in place along both sides.



Invisible zipper

This type of zipper looks different from other zippers because the teeth are on the reverse and nothing except the pull is seen on the front. The zipper is inserted before the seam is sewn. A special invisible zipper foot is required.



Mark the seam allowance with basting stitches.

Place the center of the zipper over the baste line, right side of zipper to right side of fabric. Pin in place.



Undo the zipper. Using the invisible zipper foot, sew from the top of the zipper down as far as possible. Stitch under the teeth. The machine will stop when the foot hits the zipper pull.



Do the zipper up. Place the other piece of fabric to the zipper. Match along the upper edge. Pin the other side of the zipper tape in place.



5 Open the zipper again. Using invisible zipper foot, sew down the other side of the zipper to attach to the second piece of fabric. Remove any basting stitches.



Close the zipper. On the wrong side at the bottom of the zipper, the two rows of stitching that hold in the zipper should be finishing at the same place.

.. Free end of zipper tape

Zipper. Use the normal machine foot for this. There will be a gap of about ½in (3mm) between the line for the zipper and that for the seam.





Sew the last 11/4 in (3cm) of the zipper tape to just the seam allowances. This will stop the zipper from pulling loose.



 $\label{eq:completely} On the right side, the zipper is completely invisible, with just the pull visible at the top. Apply a waistband or facing and press.$




POCKETS

Pockets

Pockets come in lots of shapes and formats. Some, such as patch pockets, are external and can be decorative, while others, including front hip pockets, are more discreet and hidden from view. They can be made from the same fabric as the garment or from a contrasting fabric. Whether casual or tailored, all pockets are functional.

Directory of pockets








KANGAROO POCKET

Unlined patch pocket

An unlined patch pocket is one of the most popular types of pocket. It can be found on garments of all kinds and be made from a wide variety of fabrics. On lightweight fabrics, such as used for a shirt pocket, interfacing is not required, but on medium and heavier fabrics, it is advisable to apply a fusible interfacing.








Lined patch pocket

If a patch pocket is to be lined, it needs to be cut with the top edge of the pocket on a fold. Like an unlined pocket, if you are using a lightweight fabric, an interfacing may not be required, whereas for medium-weight fabrics, a fusible interfacing is advisable. A lined patch pocket is not suitable for heavy fabrics.



1 Cut the pocket fabric and apply a fusible interfacing, if needed.

Pold the pocket in half, right side to right side. Pin to secure.



Trim one side of the seam allowance down to half its width.

Use pinking shears to trim the corners.



Sew around the three open sides of the pocket. Leave a gap of 1 in (3cm) for turning through.

Remove bulk from the corners by trimming.




Turn the pocket through the gap to the right side. Press.

Hand stitch the gap (using a flat fell or blind hem stitch) in the seam. The pocket is now ready to be attached.

Square patch pocket

It is possible to have a patch pocket with square corners. This requires mitering the corners to reduce the bulk.

Use a fusible interfacing on medium-weight fabrics.




Cut the pocket and apply interfacing, if needed. Neaten the upper edge of the pocket with serger or zigzag stitching.

Pold over the upper edge and stitch down the sides.

 $\operatorname{\mathsf{Sold}}$ Fold in the other three edges and press to crease.

Remove the top corners.

 $^{\cdot}$ $^{\cdot}$ Fold in the bottom corners, then fold across these to give creases for the miters.



Attaching a patch pocket

Mark the pocket placement lines on the garment with

To attach a pocket well, accurate pattern marking is essential. It is best to do this by means of tailor's tacks or even trace basting. If you are using a checker or striped fabric, the pocket fabric must align with the checkers or stripes on the garment.



Take the completed pocket and place it to the fabric, in matching the corners with the tailor's tacks. Pin in position.



Sew approx 1/32in (1mm) from the edge of the pocket.

of the pocket.

To make sure the pocket

position, baste around the edge along the sides and bottom.

Keep the basting stitches close to the finished edge



Remove the basting stitches. Press.



Alternatively, the pocket can be hand sewn in place, using a slip hem stitch into the underside of the pocket seam. Do not pull on the thread too tightly or the pocket will wrinkle.

Reinforcing pocket corners

On any patch pocket, it is essential to reinforce the upper corners as these take all the strain when the pocket is being used. There are several ways to do this, some of which are quite decorative.

REVERSE STITCH

Reinforce the corner with a reverse stitch. Make sure the stitches lie on top of one another.....



 \sum Pull the threads to the reverse to tie off.

DIAGONAL STITCH

This technique is used primarily on shirts. When sewing the pocket in place, sew along horizontally for four stitches.



Turn and sew diagonally back to the side, to create a triangular shape in the corner.

ZIGZAG STITCH

Using a small zigzag stitch, width 1.0 and length 1.0, sew diagonally across the corner.



Make a feature of this stitch by using a thread in a contrasting color.

PARALLEL ZIGZAG STITCH




Place a patch on the wrong side of the garment, behind the pocket corner, to sew into for strength.



Using a small zigzag stitch, width 1.0 and length 1.0, sew a short vertical line next to the straight stitches.

Making a pocket flap

On some styles of garment, there is no pocket, just a flap for decorative purposes. The flap is sewn where the pocket would be, but there is no opening under the flap. This is to reduce the bulk that would arise from having the rest of the pocket.




The flap consist of two pieces—a piece of lining and a piece of interfaced fabric. Place the two pieces together, right side to right side.

Match the tailor's tacks, then pin to secure.



Sew the pocket flap together along three sides, using $\frac{1}{2}$ a $\frac{1}{2}$ in (1cm) seam allowance. Sew through the tailor's tacks. Leave the upper edge open.




Turn the flap through to the right side. Push out the point.



Press the lining toward: the back so that it does not show. Press a smooth curve.

Sew across the upper : open edge to hold together.





Sew in place over the sewn line, holding the gap at the upper edge together.

Reduce the seam allowance by half. Press.



Front hip pocket

On many pants and casual skirts, the pocket is placed on the hipline. It can be low on the hipline or cut quite high as on jeans. The construction is the same for all types of hip pockets. When inserted at an angle, hip pockets can slim the figure.

Apply a piece of fusible tape on the garment along the line of the pocket.



Place the pocket lining to the front, right side to right side. Match any notches that are on the seam. Pin in place.




Sew the lining in place taking a %in (1.5cm) seam allowance.



Trim the lining side of the seam allowance down to half its width

Open out the pocket and press the seam toward the lining.



On the right side of the garment, pin the pocket bag securely along the pocket opening.



Wrong side of garment

Take the side front section that incorporates the pocket bag and place to the lining: pocket section, right side to right side. Match any seams and tailor's tacks. Pin in place.



Sew the pocket bag together using a %in (1.5cm) seam allowance. Press.



Neaten the raw edges of the seam allowance around the pocket.


Neaten the side seam allowance, stitching from the top down. Make sure the fabric lies flat where it joins the side seam.



13 The angled front hip pocket from the right side.

Kangaroo pocket

This is a variation on a patch pocket. It is a large pocket that is often found on aprons and the front of hooded sweatshirts. A half version of this pocket also features on casual jackets.







 $\dot{5}$ Turn under all the remaining edges of the pocket to the wrong side. If the fabric is bulky, miter the corners. Press in place.



Place the pocket to the garment, wrong side of the pocket to right side of the garment. Make sure the pocket is sitting flat and straight. Pin in place.



Sew the pocket along the upper edge.

Sew the short straight sides and lower edge of the pocket. Press.



Reinforce the corners of the pocket with a diagonal zigzag stitch (see page 146). 1 O If required, stitch one or two vertical lines down the center of the pocket, to divide into two pockets. Press.




WAISTLINES, BELTS, AND TIE-BACKS


Waistlines

Waistlines can be formed where a bodice and skirt join together or at the waist edge of a skirt or pair of pants. Some waistlines are attached separately to the garment to create a feature and others are more discreet. They may be shaped to follow the contours of the body.


Directory of waistlines



WAISTLINE WITH A CASING




GATHERED WAISTLINE



BASIC STRAIGHT WAISTBAND

Joining a fitted skirt to a bodice

Many dresses feature a straight fitted skirt attached to a fitted dress bodice. When joining them together, it is important that the darts or seamlines on the bodice line up with those on the skirt.



Joining a gathered skirt to a bodice

When attaching a gathered skirt to a fitted bodice, the gathers must be distributed evenly around the waist. If there are seams on the gathered skirt, these must be matched to the bodice seams and darts.




Making a casing at the waist edge

An elastic waist is featured on both skirts and pants and also at the waist on casual jackets. The casing can be made by using a deep waist seam or by attaching a facing. The facing will form a complete circle that will be attached to the waist edge.

Pin one end of the elastic to the fabric

USING A DEEP WAIST SEAM AS A CASING

Cut a piece of non-roll elastic the





Sew the lower edge of the fold 1/16in (2mm) from the edge.
Leave a 1 in (3cm) gap to insert the elastic through.



Pull the two ends of the elastic together and machine to join in a square shape with an X for strength.



Push the elastic into the casing and sew across the gap.

Pin a safety pin to the other end and thread through the casing.

154

Waistlines, belts, and tie-backs

USING A FACING AS A CASING

Cut the facing, and join the facing sections together at the side seams. Press open. Gap where facing seam has Do not join the remaining seam, but press back the seam allowances. been left open) Pin the facing to the raw edge Sew the facing Layer the around the edge seam and of the garment. press as stitched. Press the facing on to the wrong side Turn down the lower edge of the Open seam facing by 5/8 in (1.5cm). of the garment. on facing Seam on garment Sew down the facing at the folded edge, Insert the elastic into the facing and leaving a gap for the elastic to be inserted. secure the ends.

Applied casings


Some elastic waists will require the application of extra fabric to make a casing into which the elastic can be inserted. The casing may be applied to the inside or the outside of the garment. A quick way is to make the casing with bias binding. The casing can also be made from the same fabric as the garment or from a facing.

INTERNAL CASING

This type of casing is often used on a shirt-waisted dress or on a blouson-style jacket. Cut a strip of fabric on the straight of grain wide enough to accommodate your elastic and turnings.




Turn under the edge at one end by 5% in (1.5cm) and then the same along the sides. Press.



INTERNAL CASING USING BIAS BINDING


Be sure to use bias binding that will be wide enough to insert an elastic through after it has been sewn down. Apply the bias to the waistline and sew at 1/1 sin (2mm) from either edge.



Insert the elastic and knot the ends.

EXTERNAL CASING

Cut a strip of straight grain fabric $1\frac{3}{6}$ in (3.5cm) wide x the waist measurement on the garment. Turn under all raw edges by $\frac{3}{16}$ in (5mm) and press.




Place this casing over the garment waistline, with the short ends to the center front.

Sew in place along the long edges. Insert elastic to fit the waist.

Mock casings

There are several ways to construct mock casings. The simplest is to sew on elastic at the waist. An alternative, if a bodice and skirt have a waist seam joining them together, is to insert elastic between the seam allowances. On many garments, there is elastic at the back only, in a partial casing, and a waistband interfacing at the front.

STITCHING ON ELASTIC TO MAKE A WAISTLINE







lelasticated waistline.

CASING IN A WAIST SEAM ALLOWANCE





Sew again 5/8 in (1.5cm) from this line, \triangle 3 /16in (5mm) from the raw edge.



Neaten the edge of the seam using: a 3-thread serger stitch or a zigzag stitch.



Insert elastic into the casing that: \dagger you have made, with the help of a safety pin.

ALTERNATIVE CASING USING A SEAM ALLOWANCE





↑ Top-stitch the seam allowances open, stitching %in (1cm) from the seam, to make a channel either side of the seam.



3 Using a cord elastic and a bodkin, insert a length of elastic through each channel.

Knot the elastic together, then gather the fabric along the elastic to the required measurement.



Knot the elastic together at the other end and cut: off any excess.

PARTIAL CASING

with the serger

or a zigzag stitch.

The front waist is made by using an extended waistband. This means the waistband has been cut in one piece together with the skirt front. Apply a fusible interfacing to the waistband allowance.



on to the skirt, and sew at

the lower edge to secure.

On the back of the skirt, fold down the waist allowance.

Top-stitch close to the fold at the upper edge.

edge and sew to

make a casing.

Gathered back Front waist with waist stiffening

Join the skirt front to the Press the seam open

back, right side to right side,

at the side seams.


Insert the elastic with a safety:

pin. Pull up the elastic to the required length and secure by sewing it down.

Press the seam open. 1 On the right should be in

Attaching a straight waistband

A waistband is designed to fit snugly but not tight to the waist. Whether it is shaped or straight or slightly curved, it will be constructed and attached in a similar way. Every waistband will require a fusible interfacing to give it structure and support. Special waistband interfacings are available, usually featuring slot lines that will guide you where to fold the fabric. Make sure the slots on the outer edge correspond to a 5% in (1.5cm) seam allowance. If waistband fusible interfacing is not available, you can use a medium-weight fusible interfacing.



Cut the waistband and apply the interfacing. Neaten one long edge.


Pin the waistband to the skirt waist edge, right side to right side. Match the notches.



Waistband extension to be finished

Stitch the waistband to the waist edge using a 5/sin (1.5cm) seam allowance. The waistband will extend beyond the zipper by 5/sin (1.5cm) on the left and 2in (5cm) on the right.

Press the waistband away from the skirt.



5 Fold the waistband along the crease in the interfacing, right side to right side. The neatened edge of the waistband should extend %in (1.5cm) below the stitching line.

Pin the end of the waistband in line with the centre back.



7 On the right-hand back at the waist, fold the waistband in half, right side to right side.

Extend the waist/skirt stitching line through the waistband and through the end.



Turn the ends of the waistband to the right side. The extension on the waistband should be on the right-hand back. Add your chosen fasteners.




To complete the waistband, sew through the band to the skirt seam. This is known as stitching in the ditch.



The finished straight waistband.

A waist with a facing

Many waistlines on skirts and pants are finished with a facing, which will follow the contours of the waist but will have had the dart shaping removed to make it smooth. A faced waistline always sits comfortably to the body. The facing is attached after all the main sections of the skirt or pants have been constructed.




Finishing the edge of a waistband

One long edge of the waistband will be sewn to the garment waist. The other edge will need to be finished, to prevent fraying and reduce bulk inside.



This method is suitable for fine fabrics only. Turn under 5/sin (1.5cm) along the edge of the waistband and press in place. After the waistband has been attached to the garment, hand sew the pressedunder edge in place.



This method is ideal for fabrics that fray badly and can add a feature inside the garment. It is left flat inside the garment after construction. Apply a ¾in (2cm) bias binding to one long edge of the waistband.

Belts

A belt in a fabric that matches the garment can add the perfect finishing touch. Whether it be a soft tie belt or a stiff structured belt, it will be best if it has an interfacing of some kind—the firmer and more structured the belt, the firmer the interfacing should be. A belt will also need belt loops to support it and prevent it from drooping.

Directory of belts and tie-backs



STRAIGHT BELT



TIE BELT



OBI SASH



STRUCTURED CURTAIN TIE-BACK


Reinforced straight belt

This is a straightforward way to make a belt to match a garment. It can be of any width as it is reinforced with a very firm fusible interfacing, such as a craft interfacing. If one layer of interfacing is not firm enough, try adding another layer. The interfacing should be cut along its length to avoid joins.

Cut the interfacing to the dimensions of the finished belt. Cut the fabric to twice the width of the interfacing plus

) Fuse the cut ...


Fold the fabric in half lengthwise and press to mark the center line. Place the interfacing along the crease, leaving the fabric longer at the pointed end of the interfacing.



Tie belt


A tie belt is the easiest of all the belts to make. It can be any width and made of most fabrics, from cottons for summer dresses to satin and silks for bridal wear. Most tie belts will require a light to medium-weight interfacing for support. A fusible interfacing is the best choice as it will stay in place when tied repeatedly. If a very long tie belt is required, the belt can be joined at the center back.

Cut fabric for the belt, with a point at each end. Cut a fusible interfacing the same length, but half the width.



Place the interfacing on one half of the fabric on the wrong side and press to fuse.

 $\label{eq:continuous} Signature Fold the belt in half, right side to right side so the fusible is showing. Pin.$



Sew along all the raw: edges using a 5% in (1.5cm) seam allowance. Remember to leave a gap of approx. 3in (8cm) at the center back to turn the belt through.

Layer the seam by removing half of the seam allowance on the fused side.



Remove the bulk from the corners.

Press the seam as stitched,: then turn through while the fabric is still warm.

Once the belt has been turned to the right side, press the seam carefully so that it is on the very edge.



Press the points carefully.


1 O Wrap around the: waist and tie as required.

Obi sash

An obi sash is a variation of the traditional sash that is worn with a kimono. This type of sash has a stiffened center piece with softer ties that cross at the back and then wrap to the front and tie. If you are using a firm fabric such as silk dupion, satin, or heavy cotton, interfacing will not be required for the ties.

Make the ties first. Cut long strips of fabric of the required length and width......


Pold the ties lengthwise in half, right side to right side, and pin.....



Sew the long, raw edges together. Sew across the angled end.


Trim the pointed corners.

Turn the tie ends to the right side and press.




Thuse the interfacing to the wrong side of one piece of fabric. If one layer of interfacing does not make the fabric stiff enough, add another layer.

Center the tie ends to the short ends of the stiffened center piece on the right side. Sew to secure, using a ³/₆in (1cm) seam allowance.




Place the non-stiffened: fabric center piece on top, right side to right side, and pin around the edge.

1 O Fold up and tuck: the tie ends inside, between the two layers of fabric.




12 Remove the surplus fabric from the corners.



1 3 Clip the curved edges:
1 of the center section
in the seam allowance.

Pull the tie ends through the gap at the lower edge.



15 Turn the center section through to the right side and press.

Hand sew, using a flat fell or blind hem stitch, the gap at the lower edge.



The finished obi sash.

Curtain tie-backs

Tie-backs are used to hold the drape of a curtain in position. Some are structured, with an interfacing, and follow a predetermined shape, while others are softer and more decorative. The construction of a tie-back is similar to that of a tie belt.

STRUCTURED TIE-BACK



DECORATIVE RUCHED TIE-BACK

Cut a piece of batting 10in (25cm) wide and to the required tie-back length.

Roll up the batting like a sausage, but not too tight, and pin in place.....





3 Using a bold-colored thread, herringbone stitch the raw edge down to hold it in position. Make sure the rolled batting is the same thickness throughout.

For the outer decorative layer, cut a piece of fabric 5in (12cm) wide and three times the required length.


Fold lengthwise in half, right side to right side.


Sew the long raw edges together using a ³%in (1cm) seam allowance.

Stitch again, between the stitching line and the raw edge.

The double stitching is for strength.

Turn the decorative top layer fabric through to the right side and press.





Tie the thread ends from the herringbone stitch on the batting to a loop turner.

1 Using the loop turner, pull the: batting sausage through the decorative layer. This is difficult as it will stick. Work the decorative fabric gently down the batting.



Hand sew about every 1 1/4 in (3cm) to secure the ruching on the tie-back.



Ruche the decorative fabric up around the batting, evening out the fabric with your fingers. Remove the loop turner.



 $13^{\rm Sew}$ on a curtain ring at each end, using a buttonhole stitch to secure the rings.




FACINGS AND NECKLINES


Facings and necklines

The simplest way to finish the neck or armhole of a garment is to apply a facing. The neckline can be any shape to have a facing applied, from a curve to a square to a V, and many more. Some facings and necklines can add interest to the center back or center front of a garment.

Directory of necklines




ROUND NECK SCOOP NECK SQUARE NECK



Applying interfacing to a facing


All facings require interfacing. The interfacing is to give structure to the facing and to hold it in shape. A fusible interfacing is the best choice and it should be cut on the same grain as the facing. Choose an interfacing that is lighter in weight than the main fabric.

INTERFACING FOR HEAVY FABRIC



For a heavy-weight fabric use a medium-weight fusible interfacing. Remove the seam allowance on the interfacing on the inner curve to reduce bulk.


INTERFACING FOR LIGHT FABRIC



For a light to medium-weight fabric, choose a lightweight interfacing and fuse it over the complete facing.

Construction of a facing

The facing may be in two or three pieces in order to fit around a neck or armhole edge. The facing sections need to be joined together prior to being attached. The photographs here show an interfaced neck facing in three pieces.




Neatening the edge of a facing

The outer edge of a facing will require neatening to prevent it from fraying, and there are several ways to do this. Binding the lower edge of a facing with a bias strip makes the garment a little more luxurious and can add a designer touch inside the garment. Alternatively, the edge can be sewn or pinked (see opposite page).



Making your own bias strip is easy (see opposite page). Open out one folded edge of the bias strip and place to the outer edge of the facing, right side to right side.

Sew along the crease line in the bias.



Wrap the bias around to the wrong side of the work. Baste to hold in place.



Working from the right side of the facing, stitch in the ditch made by sewing the bias to the facing.



On the right side of the facing, the bias-bound edge has a neat, professional finish.

HOW TO CUT BIAS STRIPS



Fold the fabric on to itself at 45 degrees so the selvage edges are at right angles to each other. Pin in place.



Using tailor's chalk and a ruler, mark lines 1½ in (4cm) apart.

Cut along these lines to make bias strips.



Join the strips by placing them together right side to right side at 90 degrees to each other.

Sew across the join. There should be a triangle of fabric at either end of the seam.

Press the seam open.....

Press under the edges of the bias strip with the iron by running the bias strip through a 1 in (25mm) tape maker.



Other neatening methods


The following techniques are alternative popular ways to neaten the edge of a facing. The one you choose depends upon the garment being made and the fabric used.

SERGED



The outer edge neatened with a 3-thread: serger stitch.

PINKED



Machine stitch ³/sin(1cm) from the edge and the raw edge trimmed with pinking shears.

ZIGZAG




The outer edge neatened with a zigzag stitch.

Facing a slashed neckline

A slashed V-neckline occurs at either the center front or the center back neck edge. It enables a close-fitting neckline to open sufficiently to go over the head.

Apply a fusible interfacing to the facing (see page 171).
Place the facing right side to right side on garment, to the right side of the neckline.

3 Sew the facing at the neck edge, pivoting to sew along both sides of the slash between the tailor's tacks. Take one stitch horizontally at the bottom edge of the slash line.



Match the shoulder seams, then pin in place.



Cut straight down the slash line between the stitching lines.



7 Snip off the upper corners.


Clip into the corners at the bottom edge of the slash.



Turn the facing to the inside of the neckline and press.


Attaching a neck facing

This technique applies to all shapes of neckline, from round to square to sweetheart.




Pin the facing in place, matching around the neck edge.

Machine in place Ousing a %in (1.5cm) seam allowance.



right side up. Place the facing on top, right side to

Match the shoulder seams.




Match the shoulder seams On the facing and the bodice.



Trim the facing side of the seam down to half its width.

Clip V shapes around the neck edge.

right side.




Clip into the facing side of the seam as well.

Press the seam allowance toward the facing.



Understitch by sewing the seam allowance down on to the facing about 3/16in (5mm) from the sewn line.



Press the limished the wrong side. Press the finished neck edge and turn the facing toward

Bound neck edge

Binding is an excellent way to finish a raw neck edge. It has the added advantage of being a method that can be used if you are short of fabric or you would like a contrast or decorative finish. You can use bought bias tape or a bias strip cut from the same or a contrasting fabric (see page 173). A double bias strip is used on fine fabrics.

BIAS-BOUND NECK EDGE VERSION 1



Open out one edge of the bias strip and place the crease line on the ⁵/sin (1.5cm) stitching line. Pin in place.



Sew in place along the crease line.

Trim away the surplus fabric from the seam allowance.



Clip the neck seam if required.



Sew the bias strip on the inside of the garment. Press.

BIAS-BOUND NECK EDGE VERSION 2



This technique is used on bulkier fabrics. Cut a bias strip 23/4 in (7cm) wide.

Pin to the neck edge.



Sew along the neck edge using a 5/4 in (1.5cm) seam allowance.

Trim the seam allowance to half on the garment side.



Fold the raw edge of the bias to the wrong side, to touch the sewn line.

Told again to bring the folded edge of the bias to the same place, and pin.



Sew permanently in position using a flat fell stitch.

Armhole facing

On sleeveless garments, a facing is an excellent way of neatening an armhole because it is not bulky. Also, as the facing is made in the same fabric as the garment, it does not show.

Construct the armhole facing (see page 171) and neaten outer edge by preferred method.

Place the facing to the armhole, right side to right side. Match at the shoulder seams and at the underarm seam.

Sew around the armhole to attach the facing, taking a %in (1.5cm) seam allowance.





Match the notches, one at the front and two at the back. Pin the facing



allowance down to half. Clip out some V shapes in the seam:

allowance to reduce bulk.



On the underarm and shoulder seams, secure the facing to the seam allowance with cross stitches.



Press the edge. On the right side, \supset the armhole will have a neat finish.



7 Turn the facing into position on the: wrong side. Understitch by pressing the seam allowance on to the facing and sewing down.

Extended facing

A facing is not always a separate unit. Many garments, especially blouses, feature what is known as an extended facing, which is where the facing is an extension of the front of the garment, cut out at the same time.


Mark the foldline that divides off the facing area and crease by pressing.



Apply fusible interfacing to the facing area as far as the foldline.



Fold the facing back, right side to right side. Match around the neck and pin.



Sew around the neck edge to join the facing to the garment.

Trim the facing side of the seam and clip the seam allowance.



7 Turn through to the right side and press.




COLLARS

Collars

All collars consist of a minimum of two pieces, the upper collar (which will be on the outside) and the under collar. Interfacing, which is required to give the collar shape and structure, is often applied to the upper collar to give a smoother appearance to the fabric.


Directory of collars



Flat collar

A flat collar is the easiest of all the collars to construct, and the techniques used are the same for most other shapes of flat collar and facings.

Cut out the fabric for the collar accurately. Make sure the two halves match.



Cut out a fusible interfacing, being sure to cut on the same grain as the collar. Apply the interfacing to the upper collar.

Insert tailor's tacks at the center front point of the collar where indicated by a dot on the pattern piece.

Trim the under collar seam allowance to half of its width, which will reduce the bulk.




Trim around the curve with pinking shears, reducing both layers. This will allow the fabric to turn.



Working from the inside of the collar, push all the seam allowance toward the under collar and sew it to the under collar. This is called understitching and will hold the collar in shape.

1 2 Understitch as far through the curve as you can.

Pin the upper collar and under collar together, right side to right side. Match any notches and make sure the cut edges match.



Sew ⁵%in (1.5cm) along the raw outer curved edge to the lower edge of the collar. Make sure the stitches at the center front goes through the tailor's tack. If you have problems sewing a curve, mark the fabric first with chalk.

Clip the curve on the collar using small cuts at 90 degrees to the sewn line, clipping through the pinked seam.



Press the seam allowance of the upper collar on to the collar.

1 O While the collar is still warm from the steam iron, turn to the right side.



Press the curved edge flat, making sure the seam is pushed out completely on the right side.

Attaching a flat collar

A flat collar can be attached to the neckline by means of a facing. Depending upon the style of the garment, the facing may go all around the neck, which is usually found on garments with center back openings, or just be at the front.

The collar with no back facing has to be attached to the garment in stages.

FLAT ROUND COLLAR WITH NO BACK FACING



Place the collar to the neckline, right side to right side. Match the notches.

. Grown-on front facing, interfaced to foldline

Pin in place, pinning just to the tailor's tacks.


. Snip the collar at the tailor's tacks. The collar should be loose across the back neck.




Sew the under collar across the back of the neck first, from tailor's tack to tailor's tack. Do not sew the upper collar.

Match the tailor's tacks in the collar...
and facing, and match the notches.








At the center back, turn under the seam allowance on the upper collar and hand sew across the back neck with a flat fell or blind hem stitch.



FLAT ROUND COLLAR WITH A FULL FACING



- Join the front and back facing at the I shoulders. Neaten the outer edge.
 - → Join collars together, right side ✓ to right side.
 - 3 Clip the two collar sections.
 - Pin the collar to the neck edge, matching notches.....



- At the center back, fold the back: facing over the collar.
- Pin the facing over the collar. Match notches and shoulder seams.



- Layer the facing side of the seam.
- A Layer a small amount off the collar.
- Clip V shapes.



Turn to the wrong side and understitch.



Turn to the right side and press.

Mandarin collar

This collar stands upright around the neck. It is normally cut from a straight piece of fabric, with shaping at the center front edges. For a very close-fitting stand collar, the collar is cut with a slight curve.



Apply a fusible interfacing to the upper collar (see page 183). Insert any tailor's tacks as indicated on the pattern.

Pin the upper collar, interfacing side out, to the neckline of the garment, matching any notches and tailor's tacks at the center front edge.

Sew the upper collar to the neckline using a $\frac{5}{10}$ in (1.5cm) seam allowance. Make sure stop at the tailor's tack at the front edge.



A Reduce the seam allowance on the upper collar by half.

Clip through the seam allowances—this will allow the fabric to relax into shape when pressed later.



Working from the wrong side of the garment, turn in the center front edge as indicated by the pattern. This will leave the front edge of the collar sticking out from the garment.



Pin the under collar to the upper collar, right side to right side, along the top edge.

Sew the two pieces together using a %in (1.5cm) seam allowance.

At the center front, the reduced neck seam allowance needs to be pointing up into the collar, so that the seam line attaching the two collar sections together goes over it. Be sure the seam is in line with the center front of the garment.



Reduce the seam allowance to half its width on the under collar side of the seam (the non-interfaced side).

Clip V shapes out of the seam allowance to reduce the bulk. Be careful not to cut through the stitches.



Press the seam as it has been sewn, and while warm turn to the right side.

Turn under the lower edge seam allowance on the under collar and tack in place around the neck edge.



Make sure the two leading front edges of the collar are symmetrical.

Use a flat fell stitch to secure the under collar at the neck edge.

Shawl collar

A shawl collar, which is a deep V-neck shape that combines both collar and lapel in one, gives a flattering neckline that is often found on blouses and jackets. Although the collar looks complicated, it is straightforward to make. The under collar is usually part of the front of the garment.

Join the garment fronts together at the center back and press the seam open.

Stay stitch the corner of the neck/shoulder at the top of the dart through the tailor's tack.



Slash to the tailor's tack.

A Make the darts in the front—these will form the roll line of the collar.



5 Join the back sections of the garment together at the center back and press the seam open.

Join the front to the back across the shoulder seams, stopping at the slash.



Join the front of the garment to the back across the back neck, working from slash line to slash line. Press open.



Apply a fusible interfacing to the upper collar (see page 183). Tailor tack to mark the shoulder/neck point.

Join the two upper collar sections together at the center back.



Pin the upper collar to the garment, matching the center back seams and any notches. Sew in place using a 5/4 in (1.5cm) seam.

Trim the seam allowance on the under collar side (the non-interfaced side) by half. Clip V shapes into the seam to reduce the bulk.

1 Press the seam as it has been sewn and turn to the right side while still warm.

Press on the right side so the seam falls slightly to the wrong side, to avoid it showing on the right side.



At the back neck, turn under the raw edge and hand sew in place with a flat fell stitch. Neaten the other raw edges of the upper collar by your preferred technique.







SLEEVES AND SLEEVE FINISHES


Sleeves

A few sleeves, such as the dolman, are cut as part of the garment, but most sleeves, including set-in and raglan, are made separately and then inserted into the armhole. Whichever type of sleeve is being inserted, always place it to the armhole and not the armhole to the sleeve—in other words, always work with the sleeve facing you.






SET-IN SLEEVE (SHORT)




SET-IN SLEEVE (LONG)



CAP SLEEVE



DOLMAN SLEEVE



PUFF SLEEVE

Inserting a set-in sleeve

A set-in sleeve should feature a smooth sleeve head that fits on the end of your shoulder accurately. This is achieved by the use of ease stitches, which are long stitches used to tighten the fabric but not gather it.





Sew the seam of the sleeve and press open. Neaten seams. Turn the sleeve to the right side.

. Double notch denotes back of the sleeve

Around the sleeve head, work two rows of long stitches between the notches—one row at ¾in (1cm) from the edge and the second row at ½in (1.3cm). These are the ease stitches.



Place the sleeve into the armhole, right side to right side. Match the underarm seams and the notches.

Match the highest point of the sleeve to the shoulder.

Pull up the ease stitches until the sleeve fits neatly in the armhole.

7 Pin from the sleeve side.



Sew the sleeve in, starting at the underarm seam, using a 5/8 in (1.5cm) seam allowance. Sew so that the sleeve is uppermost and sew straight over the shoulder.

Overlap the seam at the underarm to reinforce the seam.



Sew around the sleeve again 3%in (1cm) inside the seam allowance.

Trim the raw edges of the sleeve.

Right side of the garment



. Smooth (wrinkle free) sleeve head

1 Neaten the seam with a zigzag or serger stitch, then turn the sleeve through the armhole.

Flat sleeve construction

On shirts and children's clothes, sleeves are inserted flat prior to the side seams being constructed. This technique can be difficult on some fabrics, such as those firmly woven, because no ease stitches are used.

The shoulder seam on the garment should be sewn and pressed open. Place the sleeve to the armhole of the garment,



Sew the sleeve to the armhole at Match the notches: a ⁵%in (1.5cm) seam allowance. and pin.





to right side. Match the underarm seams.



Press the seam open, then turn the sleeve through the armhole, right side out.


Sew together with a %in

5(1.5cm) seam allowance.

Puff sleeve

A sleeve that has a gathered sleeve head is referred to as a puff sleeve or gathered sleeve. It is one of the easiest sleeves to insert because the gathers take up any spare fabric.

Sew stitch the sleeve, right side to right side, using a 5/8in (1.5cm) seam allowance. Press the seam open.



Between the sleeve notches, insert two rows of gather stitches, one row at 3/sin (1cm) from the raw edge and the second row at ½in (1.3cm).

between the seam and the raw edge.

Place the) sleeve into the armhole, right side to right side.

Match the underarm seams.



Pull up the gathers to make the sleeve head fit the armhole.



Pin from the sleeve side.



Working with the sleeve uppermost, sew the sleeve to the armhole. Use a %in (1.5cm) seam allowance. Overlap the seam at underarm to reinforce.



fabric by 3/16in (5mm). Neaten the seam.



Turn right side out—all the gathers will be at the top of the sleeve.

Raglan sleeve

A raglan sleeve can be constructed as a one-piece sleeve or a two-piece sleeve. The armhole seam on a raglan sleeve runs diagonally from the armhole to the neck.







Bring the front and the back of the garment together, right side to right side.


Zew the side seam of the garment and continue sewing down the sleeve.



Press the seam open, then turn the sleeve through the armhole to the ..right side.

Dolman sleeve

A dolman sleeve is cut as an extension to a garment. As the armhole is very loose, it is ideal for a coat or jacket. The dolman sleeve often has a raglan shoulder pad to define the shoulder end.





Press the seams open, then turn the sleeve through the armhole to the right side.


194

Sleeves and sleeve finishes

Sleeve edge finishes

The lower edge of a sleeve has to be finished according to the style of the garment being made. Some sleeves are finished tight into the arm or wrist, while others may have a more decorative or functional finish.


Directory of sleeve edge finishes




Sleeve hems

The simplest way to finish a sleeve is to make a small hem, which can be part of the sleeve or additional fabric that is attached to turn up. A self hem is where the edge of the sleeve is turned up on to itself. If there is insufficient fabric to turn up, a bias binding can be used to create the hem. You can use purchased bias binding or make your own bias strips.

SELF HEM





: Finished hem

196

Sleeves and sleeve edges

BIAS-BOUND HEM




 $\label{eq:cut-astrip} \begin{tabular}{ll} Cut a strip of $\frac{3}{4}$ in (2cm) wide bias binding to the required length. Attach the bias to the sleeve, right side to right side. \\ \end{tabular}$

Turn under the end of the bias, placing the fold of

the bias to the sleeve seam.

 $\dot{5}$ Sew in place using a $^{3}\!\!/_{16}$ in (5mm) seam allowance.






Elastic sleeve edge

The ends of sleeves on workwear and children's clothes are often elastic to produce a neat and functional finish.


Elastic that is ½in (12mm) or 1 in (25mm) wide will be most suitable.

Make up the sleeve and press the seam open.



Work a row of basting stitches on the foldline of the hem.





Sew to hold the turn-up in place, 1/16in (2mm) from the folded edge. Leave a 1in (3cm) gap next to the seam allowance through which you will insert the elastic.



Sew the bottom of the sleeve 1/16in (2mm) from the edge, to give a neat finish. This will also help prevent the elastic from twisting.

Cut a piece of elastic to fit the arm or wrist and insert it into the sleeve end between the two rows of machining.



Secure the ends of the elastic together, sewing an X for strength.



Turn the sleeve through the armhole and check that the elasticated edge is even.

198

Sleeves and sleeve finishes

A casing on a sleeve edge


A casing is often used on the edge of a sleeve to insert elastic into, which will allow you to gather the sleeve in a specific place. The casing may be extended, which means it is part of the sleeve, or it may be applied separately. The photographs below show an applied casing of bias binding.

by sewing.




Before the sleeve is constructed, double turn the lower edge, turning to the wrong side, and sew in place.

Apply ³/₈in (10mm) bias binding, sewing along either side.



Cut a length of elastic to fit your arm or wrist. Insert the: elastic behind the bias binding and secure at one end by sewing through all layers.





Push up the bias binding along the elastic to tighten the edge of the sleeve to fit the arm or wrist. Secure at the other end




 $\ensuremath{\bigcap}$ To complete, join the sleeve seam, matching through the elastic and casing.

 $\slash\hspace{-0.5em}$ Press the seam open, then turn the sleeve through the armhole to the right side. You can adjust the ruffles if they are not evenly placed.


Cuffs and openings

A cuff and an opening are ways of producing a sleeve finish that will fit neatly around the wrist. The opening enables the hand to fit through the end of the sleeve, and it allows the sleeve to be rolled up. There are various types of cuffs—single or double, and with pointed or curved edges. All cuffs are interfaced, with the interfacing attached to the upper cuff. The upper cuff is sewn to the sleeve.


Directory of cuffs and openings




SINGLE CUFF WITH FACED OPENING



SINGLE CUFF WITH PLACKET OPENING



SINGLE CUFF WITH BOUND OPENING




SHIRT CUFF

Faced opening


Adding a facing to the area of the sleeve where the opening is to be is a neat method of finishing. This type of opening is appropriate to use with a one-piece cuff.

Turn under the long edges and one short edge on the facing by about ¼in (3mm). Sew to secure.




Place the right side of the facing to the right side of the sleeve at the appropriate . sleeve markings.

Sew vertically up the center of the facing. Take one stitch across the top and then sew straight down the other side. Keep a distance of about ¼in (6mm) between the lines at the raw edge.



Snip between the sewn lines.


Snip with small scissors into the corners.




7 The finished opening on the right side.


Bound opening

On a fabric that frays badly or a sleeve that may get a great deal of wear, a strong bound opening is a good idea. It involves binding a slash in the sleeve with a matching bias strip.





 $\label{eq:continuous} \begin{tabular}{ll} \textbf{Working on the right side of the sleeve, pin the bias strip} \end{tabular} \begin{tabular}{ll} \textbf{Supplemental strip} \end{tabular} \begin{tabular}{ll} \textbf$











One-piece cuff


A one-piece cuff is cut out from the fabric in one piece, and in most cases only half of it is interfaced. The exception is the double French cuff (see page 207).



Two-piece cuff


Some cuffs are cut in two pieces: an upper cuff and an under cuff. The upper cuff piece is interfaced.






Shirt sleeve placket


This is the opening that is found on the sleeves of men's shirts and tailored ladies' shirts. It looks complicated, but is straightforward if you take it one step at a time.



Cut out the placket and mark the pattern dots with tailor's tacks. Only these four tailor's tacks are required.



Place the placket to the shirt sleeve, right side of the placket to the wrong side of the sleeve, sewing the tailor's tacks.




Sew a rectangular box, joining the tailor's tacks together. Make sure the rows of stitches are parallel.


Remove tailor's tacks.



Snip through the placket and sleeve straight down the center, between the rows of seams.



7 Open up the placket to the right side of the fabric and press. You will have a rectangular gap with sharp corners.




long edge of the shorter side of the placket.

Place the folded edge on top of the sewn line and pin in place.



Sew the folded edge with a ½16in (2mm) seam allowance. Stop sewing at the top of the gap.





folded edge in place. Make sure the underside of the placket is not caught by the stitches.

 $\frac{1}{5}$ Continue the sewing around the point.

Sew an X through the



through to the reverse and tie off.




On the right side, the Ocompleted placket will be neatly stitched.

Attaching a cuff

There are various types of cuff that can be attached to sleeve openings. The one-piece, over-lapped cuff works well with a bound or faced opening. A two-piece barrel cuff is usually on a sleeve with a placket opening, but works equally well on a bound opening. The double cuff, or French cuff, is for men's dress shirts and tailored shirts for both ladies and men, and may be cut in one or two sections. It is usually found with a placket or bound opening.






BARREL CUFF

Apply fusible interfacing to the upper cuff. Place it to the sleeve end, right side to right side, with a seam allowance extending at either end. Pin in place.



 $\mathbf{3}$ Place the right side of the under cuff to the right side of the upper cuff. Sew together around three sides, sewing in line with the sleeve opening.



Trim down the under cuff side of the seam.

5 Remove bulk from the corners. Press.



Turn the cuff to the right side and press.

Turn under the raw edge of the under cuff and place to the end of the sleeve. With this type of sleeve, the edge of the cuff is sewn in place.

Add buttonholes to the upper cuff and attach buttons to the under cuff.

DOUBLE FRENCH CUFF

Apply interfacing to the whole of the cuff. Attach the cuff to the sleeve end, right side to right side, using a 5/4 in (1.5cm) seam allowance.



Fold the cuff back on to itself, right side to



Sew the two sides in line with the sleeve opening.

. Trim the bulk from the seams and corners.

Press, then turn the cuff through to the right side.



Fold the cuff up in half so that it is doubled. Press.

Hand sew inside to finish the other edge of the cuff.

Insert a buttonhole through the top two layers of the cuff and sew a button on to the under cuff.



DECORATIVE TECHNIQUES

Finishing touches

Simple finishing touches can be used to good effect on many items. The term appliqué applies to one fabric being sewn to another in a decorative manner. The fabric to be appliquéd must be interfaced to support the fabric that is to be attached. Appliqué can be drawn by hand, then cut and sewn down, or it can be created by a computer pattern on the embroidery machine. The embroidery machine can also be used to create quilting, or this can be done by hand or with a sewing machine.

Hand-drawn appliqué

This technique involves drawing the chosen design on to a piece of double-sided fusible web, after which the design is fused in place on fabric prior to being sewn.

Draw a decorative shape, such as a flower, on to a piece of double-sided fusible web.

2 Using the iron, fuse the web . on to your chosen fabric.

Cut out the shape from ...

Place the shape, fusible web side down, where it is to be positioned on fabric and fuse in place.




Using a wide, close zigzagstitch, sew around the shape.

For a flower, sew on top of the fabric appliqué to make petal shapes.




Trim the appliqué fabric back to the stitched lines.

→ Complete the



There are designs available for appliqué if you have an embroidery machine. You will need to use a special fusible embroidery backer on both the fabric for the appliqué and the base fabric.

Place the base fabric and appliqué fabric in the embroidery hoop and stitch out the first part of the design.







210

Quilting

This is a technique that involves sewing through two layers of fabric, one of which is a batting. The sewing sinks into the batting, creating a padded effect. Quilting can be done by hand, with a sewing machine, or using computerized embroidery.

COMPONENTS OF QUILTING



HORIZONTAL QUILTING



Baste the batting and top fabric together. Sew double lines with spaces between. Use a stitch length of 4.0 on your machine.

DIAMOND QUILTING



Diagonally baste the batting and top fabric together.



Set the machine to a stitch length of 4.0, with the needle on the one side of the foot. Sew rows of machining diagonally across. Use the width of the machine foot as a guide to keep the rows parallel.




Sew parallel rows in the opposite diagonal directions, to create diamond shapes.



← COMPUTERIZED QUILTING

Baste the batting and top fabric together, then sew on a quilted pattern with the embroidery machine.



Baste the batting and top fabric together. Sew at random.



Roses and bows

On special-occasion wear, a rose can add a superb finishing touch. When the raw edges of a rose are exposed, as in version 2 below, it also looks great made in tweed and suiting fabrics, to add a decorative finish to a tailored jacket. A bow that is permanently fixed in place is a beautiful embellishment on bridal wear.

ROSE VERSION 1



Cut a bias strip 4in (10cm) wide.
Fold in half lengthwise, wrong side to wrong side.



Pin the raw edges together.



Insert two rows of gather stitches at the raw edge—one row at 3 kin (1cm) from the edge and the other row at 1 kin (1.3cm).



Pull up the gathers, grouping them together and leaving spaces between the groups. The groups and spaces will give the impression of petals.



Hold the lower edge of one end in your left hand and loosely wrap the strip around.




When you have a rose shape, tuck any raw edges that show into the base.

Secure at the base edge with hand stitches.

ROSE VERSION 2

Cut a bias strip 4in (10cm) wide.





Pull up the gathers into groups and spaces (see step 4 above).



 \sum Hold the end of the gathers in your left hand and wrap the strip around loosely.



The groups and spaces will pull up to give a diagonal effect. Fold in half along the sewn lines.

Secure at the base with hand stitches.

Although the edge is raw, fraying is minimal as the strip has been bias-cut.

BOW

→ To make the loops, cut a piece of silk or other fabric that is four times the length of the loop required and twice the width plus seam allowances.



Interline with dress net to the wrong side. Baste the net around the raw edge.



Fold in half, right side to right side. Sew along the raw edge leaving a %in (1.5cm) seam allowance.



Turn through Bring the short end to the to the right side. Fold so that centre. Pin in place. the seamline is


> Baste dress net to the fabric

Baste through the center, using double thread.

7Pull along the / basting stitches



Next make the two ends. Cut two pieces of Ofabric the required finished length and twice the required width plus seam allowances.




in the center.

Fold each piece of fabric in half, right side to right side, and sew along the long raw edge and at an angle at one end.

Remove bulk from the corners.

Tum through to the right side. Press.

Make sure there are sharp points.



To assemble the bow, wrap a piece of fabric around the gathered center of the loops and sew in place by hand.

1 Scrunch the raw ends of the tends together and hand sew behind the loop.

Glossary

Appliqué

One piece of fabric being stitched to another in a decorative manner.

Back stitch

A strong hand stitch with a double stitch on the wrong side, used for outlining and seaming.

Basting stitch

A temporary running stitch used to hold pieces of fabric together or for transferring pattern markings to fabric.

Bias

45-degree line on fabric that falls between the lengthwise and the crosswise grain. Fabric cut on the bias drapes well. *See also* Grain.

Bias binding

Narrow strips of fabric cut on the bias. Used to give a neat finish to hems and seam allowances.

Binding

Method of finishing a raw edge by wrapping it in a strip of bias-cut fabric.

Blanket stitch

Hand stitch worked along the raw or finished edge of fabric to neaten, and for decorative purposes.

Blind hem stitch

Tiny hand stitch used to attach one piece of fabric to another, mainly to secure hems. Also a machine stitch consisting of two or three straight stitches and one wide zigzag stitch.

Blind tuck

A tuck that is stitched so that it touches the adjacent tuck without machine stitches showing. *See also* Tuck.

Bodice

Upper body section of a garment.

Boning

Narrow nylon, plastic, or metal strip, available in various widths, that is used for stiffening and shaping close-fitting garments, such as bodices.

Box pleat

Pleat formed on the wrong side of the fabric, and fuller than a knife pleat. See also Pleat.

Buttonhole

Opening through which a button is inserted to form a fastening. Buttonholes are usually machine stitched but may also be worked by hand or piped for reinforcement or decorative effect.

Buttonhole stitch

Hand stitch that wraps over the raw edges of a buttonhole to neaten and strengthen them. Machine-stitched buttonholes are worked with a close zigzag stitch.

Button shank

Stem of a button that allows room for the buttonhole to fit under the button when joined.

Casing

Tunnel of fabric created by parallel rows of stitching, through which elastic or a drawstring cord is threaded. Often used at a waist edge. Sometimes extra fabric is required to make a casing; this can be applied to the inside or outside of the garment.

Contour dart

Also known as double-pointed dart, this is used to give shape at the waist of a garment. It is like two darts joined together. *See also* Dart.

Crease

Line formed in fabric by pressing a fold.

Cross stitch

A temporary hand stitch used to hold pleats in place and to secure linings. It can also be used for decoration.

Cross tuck

Tuck that crosses over another by being stitched in opposite directions. *See also* Tuck.

Cutting line

Solid line on a pattern piece used as a guide for cutting out fabric.

Dart

Tapered stitched fold of fabric used on a garment to give it shape so that it can fit around the contours of the body. There are different types of dart, but all are used mainly on women's clothing.

Darted tuck

A tuck that can be used to give fullness of fabric at the bust or hip. *See also* Tuck.

214

Glossary

Double-pointed dart

See Contour dart

Double ruffle

Decorative trim made from two plain ruffles where one side is longer than the other. Also a ruffle made from doubled fabric.

Drape

The way a fabric falls into graceful folds; drape varies with each fabric.

Drop

The length of fabric required to make a curtain, the "drop" being the measurement from top to bottom of the window.

Ease

Distributing fullness in fabric when joining two seams together of slightly different lengths, for example a sleeve to an armhole.

Ease stitch

Long machine stitch, used to ease in fullness where the distance between notches is slightly greater on one seam edge than on the other.

Enclosed edge

Raw fabric edge that is concealed within a seam or binding.

Facing

Layer of fabric placed on the inside of a garment and used to finish off raw edges of an armhole or neck of a garment. Usually a separate piece of fabric, the facing can sometimes be an extension of the garment itself.

Felt

A natural wool fabric can felt when it is stimulated by friction and lubricated by moisture and the fibers bond together to form a cloth. Felting can also be done in a washing machine in a hot cycle.

Flat fell seam

See Run and fell seam.

Flat fell stitch

A strong, secure stitch used to hold two layers together permanently. Often used to secure linings and bias bindings.

French dart

Curved dart used on the front of a garment. See also Dart.

French seam

A seam traditionally used on sheer and silk fabrics. It is stitched twice, first on the right side of the work and then on the wrong side, enclosing the first seam.

Fusible tape

Straight grain tape used to stabilize edges and also replace stay stitching. The heat of the iron fuses it into position.

Galloon lace

Decorative lace trim shaped on both sides, used to edge a hem.

Gathers

Bunches of fabric created by sewing two parallel rows of loose stitching, then pulling the threads up so that the fabric gathers and reduces in size to fit the required space.

Goblet pleat

Decorative curtain heading in which the fabric is stitched into narrow tubes that are then stuffed with batting. See also Pleat.

Grain

Lengthwise and crosswise direction of threads in a fabric. Fabric grain affects how a fabric hangs and drapes.

Gusset

Small piece of fabric shaped to fit into a slash or seam for added ease of movement.

Hem

The edge of a piece of fabric neatened and stitched to prevent unraveling. There are several methods of doing this, both by hand and by machine.

Hem allowance

Amount of fabric allowed for turning under to make the hem.

Hemline

Crease or foldline along which a hem is marked.

Hemming tape

Fusible tape with adhesive on both sides. Iron in place to fuse and secure hems that are difficult to hand stitch.

Herringbone stitch

Hand stitch used to secure hems and interlinings. Worked from left to right.

Herringbone weave

A zigzag weave where the weft yarn goes under and over warp yarns in a staggered pattern.

Hong Kong finish

A method of neatening raw edges, particularly on wool and linen. Bias-cut strips are wrapped around the raw edge.

Interfacing

A fabric placed between garment and facing to give structure and support. Available in different thicknesses, interfacing can be fusible (bonds to the fabric by applying heat) or non-fusible (needs to be sewn to the fabric).

Interlining

Layer of fabric attached to the main fabric prior to construction, to cover the inside of an entire garment to provide extra warmth or bulk. The two layers are then treated as one. Often used in jackets and coats.

Keyhole buttonhole stitch

A machine buttonhole stitch characterized by having one square end while the other end is shaped like a loop to accommodate the button's shank without distorting the fabric. Often used on jackets.

Kick pleat

Inverted pleat extending upward from the hemline of a narrow skirt to allow freedom when walking. *See also* Pleat.

Knife pleat

Pleat formed on the right side of the fabric where all the pleats face the same direction. *See also* **Pleat**.

Lapped seam

Used on fabrics that do not fray, such as suede and leather, the seam allowance of one edge is placed over the edge to be joined, then top-stitched close to the overlapping edge. Also called an overlaid seam.

Lining

Underlying fabric layer used to give a neat finish to an item, as well as concealing the stitching and seams of a garment.

Locking stitch

A machine stitch where the upper and lower threads in the

machine "lock" together at the start or end of a row of stitching.

Miter

The diagonal line made where two edges of a piece of fabric meet at a corner, produced by folding.

Mock casing

Where there is an effect of a casing, but in fact elastic is attached to the waist, or is used only at the back in a partial casing.

Multi-size pattern

Paper pattern printed with cutting lines for a range of sizes on each pattern piece.

Nap

The raised pile on a fabric made during the weaving process, or a print pointing one way. When cutting out pattern pieces, make sure that the nap runs in the same direction.

Notch

V-shaped marking on a pattern piece used for aligning one piece with another. Also V-shaped cut taken to reduce seam bulk

Notion

An item of haberdashery, other than fabric, needed to complete a project, such as a button, zipper, or elastic. Notions are normally listed on the pattern envelope.

Overedge stitch

Machine stitch worked over the edge of a seam allowance and used for neatening the edges of fabric.

Overlaid seam

See Lapped seam.

Pattern markings

Symbols printed on a paper pattern to indicate the fabric grain, foldline, and construction details, such as darts, notches, and tucks. These should be transferred to the fabric using tailor's chalk or tailor's tacks.

Pencil pleat

The most common curtain heading where the fabric forms a row of parallel vertical pleats. *See also* **Pleat**.

Pile

Raised loops on the surface of a fabric, for example velvet.

216

Glossary

Pill

A small, fuzzy ball formed from tangled fibers which is formed on the surface of a fabric, making it look old and worn; it is often caused by friction. To remove fabric pills, stretch the fabric over a curved surface and carefully cut or shave off the pills.

Pinking

A method of neatening raw edges of fray-resistant fabric using pinking shears. This will leave a zigzag edge.

Pin tuck

Narrow, regularly spaced fold or gather. See also Tuck.

Piped tuck

See Corded tuck

Piping

Trim made from bias-cut strips of fabric, usually containing a cord. Used to edge garments or home goods.

Pivoting

Technique used to machine stitch a corner. The machine is stopped at the corner with the needle in the fabric, then the foot is raised, the fabric turned following the direction of the corner, and the foot lowered for stitching to continue

Placket

An opening in a garment that provides support for fasteners, such as buttons, snaps, or zippers.

The simplest of all the weaves; the weft yarn passes under one warp yarn, then over another one.

Pleat

An even fold or series of folds in fabric, often partially stitched down. Commonly found in skirts to shape the waistline, but also in soft furnishings for decoration.

Pocket flap

A piece of fabric that folds down to cover the opening of a pocket.

Raw edge

Cut edge of fabric that requires finishing, for example using zigzag stitch, to prevent fraying.

The turned-back front edge of a jacket or blouse to which the collar is attached.

Reverse stitch

Machine stitch that simply stitches back over a row of stitches to secure the threads.

Right side

The outer side of a fabric, or the visible part of a garment.

Rouleau loop

Button loop made from a strip of bias binding. It is used with a round ball-type button.

Round-end buttonhole stitch

Machine stitch characterized by one end of the buttonhole being square and the other being round, to allow for the button shank

Ruching

Several lines of stitching worked to form a gathered

Ruffle

Decorative gathered trim made from one or two layers of fabric.

Run and fell seam

Also known as a flat fell seam, this seam is made on the right side of a garment and is very strong. It uses two lines of stitching and conceals all the raw edges, reducing fraying.

Running stitch

A simple, evenly spaced straight stitch separated by equal-sized spaces, used for seaming and gathering.

Stitched line where two edges of fabric are joined together.

Seam allowance

The amount of fabric allowed for on a pattern where sections are to be joined together by a seam; usually this is %in (1.5cm).

Seam edge

The cut edge of a seam allowance.

Line on paper pattern designated for stitching a seam; usually 5/sin (1.5cm) from the seam edge.

Selvage

Finished edge on a woven fabric. This runs parallel to the warp (lengthwise) threads.

Shell tuck

Decorative fold of fabric stitched in place with a scalloped edge. *See also* **Tuck**.

Shirring

Multiple rows of gathers sewn by machine. Often worked with shirring elastic in the bobbin to allow for stretch.

Slip hem stitch

Similar to herringbone stitch but is worked from right to left. Used mainly for hems.

Straight stitch

Plain machine stitch, used for most applications. The length of the stitch can be changed to suit the fabric.

Stretch stitch

Machine stitch used for stretch knits and to help control difficult fabrics. It is worked with two stitches forward and one backward so that each stitch is worked three times.

Tailor's buttonhole

A buttonhole with one square end and one keyhole-shaped end, used on jackets and coats.

Tailor's tacks

Loose thread markings used to transfer symbols from a pattern to fabric.

Toile

A test or dry run of a paper pattern using calico. The toile helps you analyze the fit of the garment.

Top-stitch

Machine straight stitching worked on the right side of an item, close to the finished edge, for decorative effect. Sometimes stitched in a contrasting color.

Top-stitched seam

A seam finished with a row of top-stitching for decorative effect. This seam is often used on crafts and home goods as well as garments.

Trace basting

A method of marking fold and placement lines on fabric. Loose stitches are sewn along the lines on the pattern to the fabric beneath, then the thread loops are cut and the pattern removed.

Tuck

Fold or pleat in fabric that is sewn in place, normally on the straight grain of the fabric. Often used to provide a decorative addition to a garment.

Underlay

Strip of fabric placed under the main fabric to strengthen it, for example under a pleat or buttonhole.

Understitch

Machine straight stitching through facing and seam allowances that is invisible from the right side; this helps the facing to lie flat.

Waistband

Band of fabric attached to the waist edge of a garment to provide a neat finish.

Warp

Lengthwise threads or yarns of a woven fabric.

Warp knit

Made on a knitting machine, this knit is formed in a vertical and diagonal direction.

Weft

Threads or yarns that cross the warp of a woven fabric.

Weft knit

Made in the same way as hand knitting, this uses one yarn that runs horizontally.

Welt

Strip of fabric used to make the edges of a pocket.

Whip stitch

Diagonal hand stitch sewn along a raw edge to prevent fraying.

Wrong side

Reverse side of a fabric, the inside of a garment or other item.

Yoke

The top section of a dress or skirt from which the rest of the garment hangs.

Zigzag stitch

Machine stitch used to neaten and secure seam edges and for decorative purposes. The width and length of the zigzag can be altered.

Index

acetate 41

acrylic fahrics /1

alpaca interfacings 45 applied casings, waist edges 156 appliqué 210 armhole facings 178 arms, measuring 69 automatic needle threaders 22
В
back stitch 49, 50 back waist, measuring 69
basting stitches 49
beading needles 22
beeswax 16
belts 162-5
bent-handled shears 13
betweens 22
bias binding
cased waist edges 156
cuff openings 202 cutting strips 173
finishing waistband edges 161
hems 106, 108, 113
neck edges 176-7
ruffles 87
sleeve hems 195, 197
tape makers 16
blanket stitch 51
blind hem foot, sewing machines 27 blind hem stitch 51, 53, 111
blind tucks 90, 91
blouses
collars 182
see also sleeves
bobbins, sewing machines 26
bodices, joining skirts to 153
bodkins 22
body measurements 68–9
boning 19
bound openings buttonholes 124
0 0 0 0 0 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1

cuffs 202

neck edges 176–7 bows 213 box pleats 98, 101 braids 19 broderie anglaise 33 buckles 163 bust, measuring 68 bust darts 94 button loops 124, 127–8 buttonhole cutters 11, 12 buttonhole foot, sewing machines 26 buttonhole stitch 50, 53 buttonholes 124–6 buttons 18, 120–23

calico 33 canvas interfacings 45 cap sleeves 190 carbon paper 15 cashmere 30 casings sleeve edges 199 waist edges 154-9 centered zippers 133, 137 chalk chalk pencils 15 tailor's chalk 15 challis 30 chambray 33 checkered fabrics, cutting out 74-6 chenille needles 22 chest, measuring 68 chiffon 37 chintz 33 clean finish hems 107 seam neatening 55 clipping lines 77 collar canvas 45 collar point turners 16 collars 180-87 computerized quilting 211 concealed zipper foot, sewing machines

concealed zippers 133, 138-9 contour darts 94, 96 corded loops 128 cordurov 34 corners patch pockets 146 stitching 57-8 stitching ruffles around 87 cotton and linen mix fabrics 40 cotton fabrics 33-6 cotton thread 20 covered buttons 120, 122-3 crepe 30 crepe de chine 37 crewel needles 22 crinkle cotton 34 cross stitch 51 cross tucks 90, 92 crotch depth, measuring 69 cuffs 200-207 attaching 206-7 bound openings 202 faced openings 201 one-piece cuffs 203 shirt sleeve plackets 204-5 two-piece cuffs 203 curtains pleats 102-3 tie-backs 162, 166-7 curved hems 109 curved seams reducing bulk 59-60 stitching 58 cutting out 70-79 cutting shears 11, 12 cutting tools 12-13

damask 34 darners 22 darted tucks 92 darts 94–7 decorations 19 decorative stitches, sewing machines 53 decorative zippers 133 denim 34 designs appliqué 210 nap and 71 diagonal bastes 49 diagonal stitch, reinforcing corners 146 diamond quilting 211 difficult fabrics hems 111 seams 63 dolman sleeves 190, 194 dots, marking 77 double bias-bound hems 113 double French cuffs 207 double piping, edges 116 double-pointed darts 96 double ruffles 84, 85 double stitch 49 double turn hems 106, 110 dress-weight linen 40 dresses, joining skirts to bodices 153 dressmaker's pins 23 drill 35 duchesse satin 37 dupioni 37

edge-stitching, pleats 101 edges facings 172-3 sleeves 195-9 stitching ruffles to 86 trims 114-17 see also hems elastic 19 sleeve edges 195, 198 thread 20 waistlines 157 elbow darts 94 embroidery appliqué 210 quilting 211 embroidery foot, sewing machines 26 embroidery scissors 11, 13 embroidery thread 21 emergency sewing kits 16 envelopes, pattern 66

equipment 10-27 extra fine pins 23 evelets 132 belts 163 eves hand-worked eyes 131 hooks and eyes 18, 129

fabrics 28-45 construction 43 cotton 33-6 cutting out 70-79 grain and nap 70-71 hems on difficult fabrics 111 interfacings 44-5 linen 40 pattern layouts 72-3 pinning pattern to 72 reducing seam bulk 59-60 seams on difficult fabrics 63 silk 37-9 wool 30-32 facings 168-79 armholes 178 cased waist edges 155 construction 171 cuffs 201 faced hems 106 flat collars 185 grown-on facing 179 interfacings 171 neatening edges 172-3 neck facings 174-5 waistlines 161 fasteners 18, 129-32 buttons and buttonholes 18, 120-28 evelets 132 hooks and eyes 18, 129, 131 snaps 18, 129, 131 tape fasteners 129, 132 zippers 10, 133-9 feet, sewing machines 26 fitted dresses, joining skirts to bodices 153 flannel 31 flaps, pocket 147

flat collars 182, 183-5 flat fell stitch 51 flat sleeves 192 flat trims, on edges 115 folds, cutting out fabrics 72, 73 14-in-1 measures 16 freeform quilting 211 French chalk 15 French darts 97 French seams 61 frills see ruffles fringes 19, 117 front hip pockets 148 fur fabric 42. seams 63 fused hems 112. fusible interfacings 44

gabardine 31 galloon lace, on edges 114 gathers 82-3 gathered piping edges 116 joining skirts to bodices 153 shirring 82 georgette 38 gingham 35 glass headed pins 23 glue pens 16 goblet pleats, curtains 103

habutai 38 hand sewing, stitches 48-51 headings elasticated sleeve edges 195 ruffles with 84, 85 height, measuring 68 hem stitch 51, 53 hems 106-13 on difficult fabrics 111 fused hems 112 hand-stitched hems 107-9 machined hems 110-12 marking a hemline 106

sleeves 195
turning up 107
see also edges
herringbone stitch 51
herringbone weave 43
hip pockets 148
hips, measuring 69
Hong Kong finish 55
hooks and eyes 18, 129, 131
horizontal buttonholes 125
horizontal quilting 211
household pins 23

in-seam buttonholes 126 inside leg, measuring 69 interfacings 44–5, 171 inverted pleats 98, 101 invisible zippers 133, 138–9 ironing boards 17 irons 17

J jersey 35

kangaroo pockets 142, 149 keyhole buttonhole stitch 53 keyhole buttonholes 124, 126 kick pleats 98, 101 knife pleats 98, 101 knitted fabrics 43, 70 knitted interfacings 44 knots, tying 48

lace trims, on edges 114 lapped cuffs 206 lapped seams 62 lapped zippers 133, 135 layering seams 59

layouts, patterns 72–3 leather 41 synthetic 42 legs, measuring 69 lightening stitch 53 linen fabrics 40 lines, clipping 77 linings, patch pockets 144 liquid sealant 16 locking stitch 52 long and short tacks 49 loop turners 16 loops, button 124, 127–8

machines accessories 26-7 appliqué 210 buttonholes 126 hems 110-12 needles 26 quilting 211 sewing machines 24-7 shirring 89 stitches 52-3 madras 35 man-made fabrics 41-2 mandarin collars 186 markers 79 marking aids 15 hemlines 106 pattern symbols on fabric 77 markings, pattern 67 matka 38 measurements, body 68-9 measuring tools 14 metal bobbins 26 metal tape measures 14 metallic thread 20 milliner's needles 22 mittens, pressing 17 mock casings, waist edges 157-9 mohair 31 multi-size patterns 67 muslin 36 interfacings 45

nap 70-71 cutting out fabrics 73 neatening seams 55-6 necklines 170 bound edges 176-7 facings 174-5 measuring 69 needles 11, 22 needle threaders 22 sewing machines 26 threading 48 non-fusible interfacings 45 non-woven interfacings 44 non-woven sew-in interfacings 45 notches, marking 77 notions 10, 18-19 novelty buttons 120 nvlon 41

obi sashes 162, 164–5
one-piece cuffs 203
one-way designs, nap and 71
open-ended zippers 133, 136
organza 39
interfacings 45
outside leg, measuring 69
overedge foot, sewing machines 27
overedge stitch 53
seam neatening 55
overlock stitch, neatening facings 173

pants
hooks and eyes 129, 131
waistlines 154–9
zippers 133–9
paper scissors 13
parallel zigzag stitch, reinforcing corners
146
patch pockets 142–6, 149
patterns 64–79
layouts 72–3

marking symbols onto fabric 77, 78-9 in-seam buttonholes 126 pinning to fabric 72 inserting trimmings in 117 preparation 71 raglan sleeves 194 marking for zipper placement 134 reading 66-7 neatening 55-6 rayon 42 symbols 67 reading patterns 66-7 reducing bulk 59-60 pearl-headed pins 23 reinforced buttons 122 stitch finishes 60 pencil pleats, curtains 103 reinforced corners 58, 146 stitching ruffles into 88 pencils, chalk 15 retractable tape measures 14 types of 61-2 Peter Pan collars 182 reverse stitch 52 securing threads 49, 52 pile, nap and 71 reinforcing corners 146 seersucker 36 pin cushions 11, 23 self-bound finish, ruffles 86 ribbons 19 pin tucks 91 rolled hem foot, sewing machines 27 self hems, sleeves 195, 196 pinking shears 13 rolled hems 106, 112 self-threading needles 22 hem finishes 108 roses 212 set-in sleeves 190, 191 neatening facings 173 rouleau loops 124, 127 sewing gauges 11, 14 round-end buttonhole stitch 53 sewing machines see machines seam neatening 55 round-end buttonholes 124, 126 pins 10, 23 shanked buttons 120, 121 piped edges 115-16 round necks 170 shantung 38 plackets, shirt sleeves 204-5 ruched tie-backs, curtains 167 sharps 22 plain darts 95 ruffles 84-8 shawl collars 87 shears 11-13 plain ruffles 84 sleeve edges 195 plain seams 54 stitching around a corner 87 sheer fabrics, seams 63 plain tucks 90, 91 stitching into a seam 88 shell tucks 90, 93 plain weave 43 stitching to an edge 86 shirring 82, 89 plastic bobbins 26 with a heading 84, 85 shirting 36 pleats 98-103 run and fell seams 61 shirts curtains 102-3 running stitch 50 cuffs 200, 204-7 edge-stitching 101 see also sleeves on the right side 99 shoulders top-stitching 101 matching stripes or checks 75 on the wrong side 100 measuring 69 pocket flaps 147 safety pins 10, 23 silk and wool mix fabrics 39 pockets 140-49 sashes, obi 162, 164-5 silk fabrics 37-9 polyester all-purpose thread 21 satin 39 single bias-bound hems 113 polyester fabrics 42 duchesse satin 37 single cuffs 200 pressing aids 17 satin weave 43 single piping, edges 115 pressing cloths 17 scissors single-size patterns 67 pressing darts 97 cutting out fabrics 77 single turn hems 106, 110 pressing mittens 17 embroidery scissors 11, 13 skirts printed linens 40 paper scissors 13 striped or checkered fabrics 75 puff sleeves 190, 193, 199 shears 11, 12 waistlines 150-61 trimming scissors 13 zippers 133-9 scoop necks 170 slashed necklines, facings 174 sealant, liquid 16 sleeves 188-99 cuffs 200-207 seam rippers 11, 12 seams 54-63 edge finishes 195-9 quilting 211 cased waist edges 158 quilting needles 22 slip hem stitch 51

corners and curves 57-8

on difficult fabrics 63

slip tacks 49

snap tape 129, 132

snaps 18, 129, 131 snips 12 spaced tucks 90, 91 spandex 42 square necks 170 stand collars 182, 186 stitch rippers 11, 12 stitches 48-63 hand sewing 48-51 machine stitches 52-3 securing threads 49, 52 stitch finishes 60 tacking stitches 49 straight stitch 52 rolled hems 112 straw needles 22 stretch knits 43, 70 stretch stitch 53 stripes cutting out fabrics 74, 76 nap and 71 suede 41 seams 63 synthetic 42, 63 suiting linen 40 sweetheart necks 170 symbols, on patterns 67, 77, 78-9 synthetic furs 42 seams 63

taffeta 39 tailor's buttonholes 126 tailor's chalk 15 tailor's ham 17 tailor's tacks 78 tape fasteners 129, 132 tape makers 16 tape measures 10, 14 tapes, pleats on curtains 102 tapestry needles 22 tartan 31 thimbles 10, 16 threading needles 48 threads 10, 20-21 securing 49 3-step zigzag stitch 52

tie-backs, curtain 162, 166-7 tie belts 162, 174 tools 10-27 top-stitching pleats 101 seams 60, 62 top-stitching thread 21 trace tacking 79 tracing paper, pattern marking 78 tracing wheels 15, 78 trimming scissors 13 trimmings 19 on edges 114-17 inserting in seams 117 tucks 90-93 tweed 32. tweezers 16 twill weave 43 twin needle tucks 91 two-piece cuffs 203 tving knots 48

U-necks

U-necks 170 understitching seams 60

V

V-necks 170 Velcro™ 18, 129, 132 velvet 36 venetian 32 vertical buttonholes 125

wadding, quilting 211
waffle shirring 82, 89
waist darts 94
waistlines 150–61
attaching straight waistbands 160
casings 154–9
elastic 157
facings 161
finishing edges 161

joining skirts to bodices 153
measuring 68
walking foot, sewing machines 27
warp knit 43
water/air-soluble pens 15
wax 16
weft knit 43
whip stitch 50
wool fabrics 30–32
worsted, wool 32
woven fabrics, grain 70
woven interfacings 44

Zigzag stitch 52 hems 108 neatening facings 173 reinforcing corners 146 rolled hems 112 seam neatening 55 zipper foot, sewing machines 27 zippers 10, 133–9

Acknowledgments

About the author

Alison Smith trained as an Art and Fashion Textile teacher, before becoming Head of Textiles at one of the largest schools in Birmingham, where she was able to pursue one of her key interests: the importance of teaching needlecrafts to boys, as well as girls. After successful spells as textiles tutor at the Liberty Sewing School, London, and the Janome Sewing School, Cheshire, Alison set up her own shop, Fabulous Fabric, and sewing school, Alison Victoria School of Sewing, in Ashbyde-la-Zouch, Leicestershire. Her school is the largest independent sewing school in England and offers courses and workshops on all aspects of dressmaking, tailoring, and corsetry.

Alison regularly lectures at specialist sewing shows, is a regular contributor to Sewing World magazine, and has appeared on ITV television series Ladette to Lady teaching dressmaking skills. She lives with her husband in Leicestershire, and has two grown-up children.

Author's acknowledgments

No book would ever be written without a little help. I would like to thank the following people for their help with the techniques and projects: Jackie Boddy, Nicola Corten, Ruth Cox, Helen Culver, Yvette Emmett, Averil Wing, and especially my husband, Nigel, for his continued encouragement and support, as well as my mother, Doreen Robbins, who is responsible for my learning to sew. The following companies have also provided invaluable help, by supplying the sewing machines, haberdashery, and fabrics: Janome UK Ltd, EQS, Linton, Adjustoform, Guttermann threads, the Button Company, YKK zips, Graham Smith Fabrics, Fabulous Fabric, Simplicity Patterns, and Freudenberg Nonwovens LP.

Dorling Kinderslev would like to thank:

Heather Haynes and Katie Hardwicke for editorial assistance; Elaine Hewson and Victoria Charles for design assistance; Susan Van Ha for photographic assistance; Hilary Bird for indexing; Elma Aguino; Alice Chadwick-Jones; and Beki Lamb. Special thanks from all at DK to Norma MacMillan for her exceptional professionalism and patience.

Picture credits:

Additional photography: Laura Knox p70 tl, tr, 72 t, 74 tr, br, 76 b

Illustrator: Debajvoti Datta

Patterns: John Hutchinson, pp66–67, 76 Additional artwork: Karen Cochrane p67 r